

# Install Recast Management Server without Recast Proxy


Last Modified on 07.21.23

Before installing Recast Management Server, ensure that your system meets the application's [hardware and software requirements](#).

Recast Management Server software can be installed on its own server or on the primary Configuration Manager server.

## Run the Recast Management Server Installer


After downloading Recast Management Server from the [Recast Portal](#), run the installer and follow its prompts.



## IIS

To configure IIS:

1. On the **IIS Configuration** page, change the **Server Name** only if the client is going to use a DNS alias.
2. Set the **IIS Port**. The default IIS Port is **TCP 444**, to prevent conflicts when Recast Management Server is installed on Configuration Manager servers. The IIS Port can be changed to 443, or any open TCP port, to suit your environment.




## Certificates

Recast Management Server requires a certificate for secure communication with Right Click Tools and any Recast Proxies.

To configure a certificate:

On the **Certificate Configuration** page, you have the option to **Generate a Self-signed Certificate** or **Use an Existing IIS Certificate** issued by a trusted internal Certificate Authority.



#### CERTIFICATE NOTES:

- The subject name or one of the subject alternative names of the certificate should match the server name in the URL that the Right Click Tools and Recast Proxies are pointed towards.
- The public key of self-signed certificates must be added to the Trusted Root Certificate Authorities store on your Recast Proxies.
- Right Click Tools will prompt for untrusted certificates and add them to an allowed list. To avoid this prompt, import the public key of the Recast Management Server certificate into the Trusted Root Certificate Authorities store on the devices where the Right Click Tools are installed.
- The certificate can be changed later by editing the Binding in IIS Manager.


## SQL Server

Recast Management Server requires SQL Server version 4.0 or higher. This can be the free SQL Server Express version, or enterprise SQL.

If the SQL Server is installed on a remote device, the computer account of Recast Management Server will need permissions to create the database on the remote device. Alternatively, you can [pre-create the RecastManagementServer database](#) and give the computer account db\_owner permissions.

If the SQL Server is installed on the local device, the computer account of the Recast Management Server will need permissions to create the database on the local device. You can pre-create the database and give the IIS AppPool\Recast Management Server account db\_owner permissions to the database.

This account will not exist until after the installation is finished, so the permissions will need to be given after installation. The **Test SQL Connection** button will verify connectivity to the SQL Server during installation if the account running the installation has permissions to remotely connect.



**Recast Management Server - Setup**

**SQL Configuration**

If you would like the installer to automatically create the database and setup permissions, add the user running setup to the sysadmin role on the SQL server before clicking Next. This role can be removed after the installation finishes.

SQL Server Name:

SQL Server Port:

Success

## SQL SERVER NOTES:

- **Remote SQL Server:** The computer account of the Recast Management Server needs to be given the db\_owner role for the RecastManagementServer database.
- **Local SQL Server:** The IIS AppPool\Recast Management Server account needs to be given the db\_owner role for the RecastManagementServer database.
- The IIS AppPool\Recast Management Server account will not exist until after the installation completes.
- The default SQL Server Port Number is 1433.
- For more information, see [Configure SQL Server Permissions](#).


## Import License

You can download and import your Recast licenses when installing Recast Management Server.

To download your Enterprise license:

1. On the **Import License** page, enter your Recast Portal email address and password.
2. Click **Download License**. The license information will appear in the right-hand column.

**NOTE:** If your server does not have internet access, click **Browse for License** to browse the filesystem for a license file that has been exported from the [Recast Portal](#).



**Recast Management Server - Setup**

**Import License**

Sign in with your Recast Software account to download your Recast RCT Enterprise License. If you do not have internet access on this computer, visit the Recast Software Portal to export a copy of your license and use the Add License button to add it.


Email:  Expiration: 8/7/2022 12:00:00 AM

Password:  Device Count: 1500

## Configure Without Recast Proxy

A Recast Proxy allows you to schedule Kiosk Manager and Builder actions as well as Recast security scopes. For instructions on installing Recast Proxy, see [Installing Recast Management Server with Recast Proxy](#).

If you do not wish to install a Recast Proxy during Recast Management Server installation, enable **Do Not Install Recast Proxy** and click **Install**.

The image shows a Windows-style setup window titled "Recast Management Server - Setup". The window has a standard title bar with a close button (X) in the top right corner. Below the title bar is a header area with the text "Proxy Configuration" and a small icon of a cube with colored faces. The main content area contains a message: "A Recast Proxy is required for scheduling Kiosk Manager and Builder actions as well as Recast security scopes." Below this message are three input fields: "Domain" with the text "corp.contoso.com", "User", and "Password". To the right of the "Password" field is a checkbox labeled "Do Not Install Recast Proxy" which is checked. Below the input fields is a button labeled "Test Credentials". Below the "Test Credentials" button is a line of text: "Click the Test Results button to verify that the credentials are valid." At the bottom of the window is a footer area containing a help icon (question mark in a circle) on the left and three buttons: "Previous", "Install", and "Cancel".

When the installation completes, click **Finish** to exit the setup wizard.

## Verify Recast Management Server Installation

To confirm that you can open the Recast Management Server, navigate to `https://<ServerFQDN>:<Port>` in a web browser. Chrome, Edge, or Firefox are recommended. On the Recast Management Server login page, enter the username and password for the account that you were using to install the Recast Management Server.