

Server Migration

Last Modified on 06.21.23


Instructions for migrating your Recast Management Server database to a new server.

To migrate the RecastManagementServer database:


1. Back up your RecastManagementServer database.
2. Copy the database over to the new location.
3. Navigate to `C:\Program Files (x86)\Recast Software\Recast Management Server` on your management server and open the **appsettings.Production.json** file.
4. Update your server information in the .json file to specify the new server name.

```
{  "ConnectionStrings": {    "DefaultConnection": "Server=localhost;Database=RecastManagementServer;Trusted_Connection=True;MultipleActiveResultSets=true"  }}
```


5. Open IIS Manager, under **Manage Website**, click to **Restart** your Recast Management Server website.



6. Under **Application Pool Tasks**, click **Recycle**.



7. If the name changes for the server, update any Right Click Tools installations to point to the new server by adding the **Recast Management Server** URL on the **General** tab in the Configure Recast Console Extension application.



8. If you have agents in your environment, update the **ServerUri** registry keys to point to the new server's name.

Agent Server Uri Registry Entry:

Registry Editor

File Edit View Favorites Help

Computer\HKEY_LOCAL_MACHINE\SOFTWARE\WOW6432Node\Recast Software\Recast Agent

Name	Type	Data
(Default)	REG_SZ	(value not set)
InstallDir	REG_SZ	C:\Program Files (x86)\Recast Software\Recast Ag...
ServerUri	REG_SZ	https://cm1.corp.contoso.com:444

WOW6432Node

- Classes
- Clients
- Intel
- Microsoft
- ODBC
- Policies
- Recast Software
 - Recast Agent
 - Endpoint Ir
- RegisteredApplic

SYSTEM

WOW6432Node

ServerUri

Edit String

Value name: ServerUri

Value data: https://cm1.corp.contoso.com:444

OK Cancel