

Proxy Permissions

Last Modified on 08.20.25

The permission set required for a proxy service account differs depending on how you're using a Recast Proxy.

If you haven't set up the required proxy permissions prior to installing Recast Management Server or Recast Proxy, you can skip the installer's **Configuration Manager Configuration** page by removing any information from the text fields, selecting **Test ConfigMgr Connection** and the **Skip ConfigMgr Verification** checkbox, and clicking **Next**.

Right Click Tools

Access web dashboards and trends Schedule Builder actions Schedule kiosk profile application	 Local admin access on the server where the proxy is being installed Read permissions in Active Directory db_datareader in the Configuration Manager SQL server database Read-only access to the Configuration Manager console (Read-only Analyst security role in ConfigMgr)
Run actions as a service account	 Local admin access on any device that actions will be run against Read/Write permissions in Active Directory (Write only required to delete devices from AD) Appropriate ConfigMgr Security Role for intended actions in the Configuration Manager console (Full Administrator for all actions) Permission to MBAM, if applicable
Elevate permissions	• Local admin access on all devices managed by Right Click Tools
Add or remove from collections	 Permission to modify a collection in Configuration Manager configmgr collection > modify permission
Fast Channel support	 Permission to run scripts in Configuration Manager If using Read-only Analyst in ConfigMgr as your base security role, also grant the following privileges: Collection > Run Script = Yes SMS Scripts > Read = True

Right Click Tools Insights

Collect warranty information	 Local admin access on the server where the proxy is being installed Read permissions in Active Directory db_datareader in the Configuration Manager SQL server database Read-only access to the Configuration Manager console (Read-only Analyst security role in ConfigMgr) NOTE: These permissions match those required to access web dashboards and trends in Right Click Tools Internet access for the proxy account in order for the Recast Management Server to reach our API at https://warranty.recastsoftware.com over TCP 443
Collect warranty information if RMS is installed on a server other than your ConfigMgr SQL database	 Add proxy account to the SMS_SiteSystemToSiteServerConnection_MP_<yoursitecode> local group on that server, allowing it to read/write to your inboxes\auth\ddm.box</yoursitecode>

Right Click Tools Privileged Access

NOTE: Privileged Access does not require a Configuration Manager service connection.

For all Privileged Access features	• Local admin on the server where the proxy is being installed
	Read permissions in Active Directory

Right Click Tools Patching

MECM Integration	• Grant any of the following built-in roles/role combinations to the proxy
	account:
	• Full Administrator
	Operations Administrator
	• Application Administrator and Compliance Settings Manager
	• Application Administrator and Read-only Analyst
	• Grant modify permissions to the SMB share (UNC path) that will be used to
	store downloaded applications
	• Access to the necessary external domains. See System Requirements.

Intune Integration	• Grant modify permissions to the SMB share (UNC path) that will be used to
	store downloaded applications
	• Access to the necessary external domains. See System Requirements.

NOTE: Group Managed Service Accounts (gMSAs) are not currently supported.

Copyright © 2025 Recast Software Inc. All rights reserved.