



Proxy Permissions

Last Modified on 10.16.24

The permission set required for a proxy service account differs depending on how you're using a Recast Proxy.

If you haven't set up the required proxy permissions prior to installing Recast Management Server or Recast Proxy, you can skip the installer's **Configuration Manager Configuration** page by removing any information from the text fields, selecting **Test ConfigMgr Connection** and the **Skip ConfigMgr Verification** checkbox, and clicking **Next**.

Right Click Tools

<p>Access web dashboards and trends</p> <p>Schedule Builder actions</p> <p>Schedule kiosk profile application</p>	<ul style="list-style-type: none"> • Local admin access on the server where the proxy is being installed • Read permissions in Active Directory • db_datareader in the Configuration Manager SQL server database • Read-only access to the Configuration Manager console (Read-only Analyst security role in ConfigMgr)
<p>Run actions as a service account</p>	<ul style="list-style-type: none"> • Local admin access on any device that actions will be run against • Read/Write permissions in Active Directory (Write only required to delete devices from AD) • Appropriate ConfigMgr Security Role for intended actions in the Configuration Manager console (Full Administrator for all actions) • Permission to MBAM, if applicable
<p>Elevate permissions</p>	<ul style="list-style-type: none"> • Local admin access on all devices managed by Right Click Tools
<p>Add or remove from collections</p>	<ul style="list-style-type: none"> • Permission to modify a collection in Configuration Manager <p>configmgr collection > modify permission</p>
<p>Fast Channel support</p>	<ul style="list-style-type: none"> • Permission to run scripts in Configuration Manager • If using Read-only Analyst in ConfigMgr as your base security role, also grant the following privileges: <p>Collection > Run Script = Yes SMS Scripts > Read = True</p>

Endpoint Insights

Collect warranty information	<ul style="list-style-type: none">• Local admin access on the server where the proxy is being installed• Read permissions in Active Directory• db_datareader in the Configuration Manager SQL server database• Read-only access to the Configuration Manager console (Read-only Analyst security role in ConfigMgr) <p>NOTE: These permissions match those required to access web dashboards and trends in Right Click Tools</p> <ul style="list-style-type: none">• Internet access for the proxy account in order for the Recast Management Server to reach our API at https://warranty.recastsoftware.com over TCP 443
Collect warranty information if RMS is installed on a server other than your ConfigMgr SQL database	<ul style="list-style-type: none">• Add proxy account to the SMS_SiteSystemToSiteServerConnection_MP_<YourSiteCode> local group on that server, allowing it to read/write to your inboxes\auth\ddm.box

Privilege Manager

NOTE: Privilege Manager does not require a Configuration Manager service connection.

For all Privilege Manager features	<ul style="list-style-type: none">• Local admin on the server where the proxy is being installed• Read permissions in Active Directory
------------------------------------	---

Application Manager

MECM Integration	<ul style="list-style-type: none">• Grant any of the following built-in roles/role combinations to the proxy account:<ul style="list-style-type: none">◦ Full Administrator◦ Operations Administrator◦ Application Administrator and Compliance Settings Manager◦ Application Administrator and Read-only Analyst• Grant modify permissions to the SMB share (UNC path) that will be used to store downloaded applications• Access to the necessary external domains. See Application Manager System Requirements.
------------------	---

Intune Integration

- Grant modify permissions to the SMB share (UNC path) that will be used to store downloaded applications
- Access to the necessary external domains. See [Application Manager System Requirements](#).