

Agent Gateways for Right Click Tools

Last Modified on 03.28.25

A Recast Agent Gateway is an on-premises component that connects your Recast Management Server to your Recast Agents. An Agent Gateway lets you to manage your endpoints at scale by providing a secure communications path for:

- Agent authentication and authorization
- Agent licensing
- Directing Recast actions to Agents
- Extending Agent connectivity to the Internet
- Connecting Agents with other Recast components


Multiple Agent Gateways can be added, meaning that there's no limit to the number of Agents that can connect to your Recast Management Server. Internet-connected devices that are not on your local network can connect to the Agent Gateway, allowing you to run Recast actions against them, without the need for a Cloud Management Gateway (CMG).

Install an Agent Gateway

A single Agent Gateway is automatically deployed and authorized when you install Recast Management Server. You can also install additional Agent Gateways, to accommodate all of your Recast Agents. Each Agent Gateway must be installed on a different server. Agent Gateway software is available from the [Recast Portal](#).


To configure an Agent Gateway:

1. On the Agent Gateway installer's IIS Configuration page, specify the **Server Name** in FQDN format (server.domain.local) and **IIS Port** for the Agent Gateway.




The screenshot shows a window titled "Recast Agent Gateway - Setup" with a close button (X) in the top right corner. Below the title bar is the Recast logo. The main content area is titled "IIS Configuration" and contains two input fields: "Server Name" with the value "GWSERVER" and "IIS Port" with the value "444". At the bottom of the window, there is a help icon (question mark in a circle) on the left and three buttons: "Previous", "Next", and "Cancel".

2. On the Certificate Configuration page, select an existing certificate, or generate a self-signed certificate.



3. Click **Test Connection** to check that the Agent Gateway can connect to your Recast Management Server.



4. With a successful connection test, click **Install**.

5. When the installation completes, click **Finish** to close the installer.

Verify Agent Gateway Installation

In the Recast Management Server interface, navigate to **Administration > Agent Gateways** and check that the new Agent Gateway is connected and authorized. If you've installed an Agent Gateway on a separate server, you may need to [manually authorize it in RMS](#).

For information on the hardware needed for Agent Gateway servers, see [Recast Management Server System Requirements](#).

To learn more about installing your Recast Management Server with an additional Gateway, see [Network Architecture: RMS with Standalone Agent Gateway](#).

The Agent Gateway SQLite file is located at `C:\Users\Recast Agent Gateway\AppData\Roaming\Recast Software\Recast Agent Gateway`

View Agent Gateways

The **Recast Agent Gateways** page in RMS displays details related to your Agent Gateways. By default, the one Agent Gateway added automatically during Recast Management Server installation is listed.

Details and actions available:

- **Computer Name**
- **Connected:** Shows whether the Agent Gateway is connected to your Recast Management Server.

NOTE: Recast Agents must enroll with the Recast Management Server before they can communicate with an Agent Gateway and be used to run actions. See [Deploy Recast Agents](#).

- **Version:** Agent Gateway software version
- **Authorized:** To manually authorize an Agent Gateway, click the Edit icon to the right of the Agent to authorize. In the **Edit Recast Agent** window, enable the **Authorized** checkbox and click **Save**.
- **Actions**
 - **Edit** Agent Gateway details or authorize an Agent Gateway.
 - **Delete** an Agent Gateway by clicking the Delete icon to the right of an Agent Gateway and confirming the deletion.

Recast Agent Gateways

Computer Name	Connected	Version	Authorized	Actions
CM1	✓	5.0.2302.1703	✓	 

1 - 1 of 1 items

NOTE: You can view the Agent Gateway to which a specific Agent is connected on the [Agents](#) page.

Delete an Agent Gateway

To delete an Agent Gateway:

1. In the Recast Management Server interface, navigate to **Administration > Agent Gateways**.
2. Click the Delete icon to the right of the Agent Gateway to remove and confirm the deletion.