



Install Recast Proxy Separately for Right Click Tools

Last Modified on 02.25.25

You can install a Recast Proxy separately if it was not installed during [Recast Management Server installation](#), or if it needs to be installed on a server other than the Recast Management Server. After installing a Recast Proxy, you'll need to [approve it manually](#) and [add service connections](#).

Proxy Uses in Right Click Tools

- [Elevate permissions](#) using a service account
- Populate [web dashboards](#) in Recast Management Server
- Populate [limiting rules](#) (required for fast channel/cloud management gateway and RMS permissions)
- Run actions against devices in a [different domain](#)
- Schedule [Builder actions](#) and [Kiosk Manager deployments](#)

Configuration Manager and Active Directory permissions vary depending on which tasks you're using the Recast Proxy for. See [Proxy Permissions](#).

The Recast Proxy SQLite file is located at `C:\Users\<Proxy Username>\AppData\Roaming\Recast Software\Recast Proxy`


Prerequisites

- [Recast Management Server installed](#)

Run the Proxy Installer


To install Recast Proxy:

1. Download the Recast Proxy installer from the [Recast Portal](#) and run it.
2. On the **Recast Server Configuration** page, enter the Recast Management **Server Name** and **Server Port** number.
3. Click **Test Connection** to make sure that the proxy can connect to the Recast Management Server.




If the installer does not connect to the Recast Management Server, the proxy will not install successfully. Troubleshoot any error messages that appear in the installer before continuing with the install.

4. On the **Service Account Configuration** page, enter the **Domain**, **Username** and **Password** that you would like to use for your proxy and click **Test Credentials** to verify service account details.




If the User Account Credentials that you enter on the Service Account Proxy Screen do not validate correctly, the Service Account Proxy will not work correctly. Troubleshoot any login errors before continuing to the next step.


5. On the **Domain Configuration** page enter your primary **Domain** and click **Test Domain Connection** to check that the service account can read from the domain.




6. On the **Configuration Manager Configuration** page, enter your **SMS Provider**, **Site Code**, **SQL Server**, and **SQL Database** information and click **Test ConfigMgr Connection** to check that your service account has permission to access your Configuration Manager environment.



7. If you have a standalone MBAM server (and are not managing BitLocker in ConfigMgr), enable **Configure MBAM** and enter the information for your MBAM environment. If you are not using an MBAM Server, leave the checkbox blank and click **Install**.



8. If you have a standalone MBAM environment, enter its details and click **Test MBAM Connection** to ensure that the service account you selected has permission to use MBAM.



9. Click **Install**.

10. After the installation completes, click **Finish** to close the installer.

Silent Install for Standalone Recast Proxy

Add the parameter `RCTENTERPRISESERVER=https://<FQDN>:<Port>` to your install string so your standalone Recast Proxy can connect to your Recast Management Server. Substitute the FQDN for your RMS server followed by the port number.

Example:

```
msiexec /i "Recast Proxy.msi" /! *v %temp%\RecastProxy.log PROXYLOGONUSER="<Domain>\<Username>" RCTENTERPRISESERVER="https://<FQDN>:<Port>" SERVICEACCOUNTPASSWORD="<Password>" SERVICEACCOUNTDOMAIN="<Domain>" SERVICEACCOUNTUSERNAME="<Username>" /qn
```