

## Recast Agent Gateways

Last Modified on 2026-05-26

A Recast Agent Gateway is an on-premises component that connects your Recast Management Server to your Recast Agents. An Agent Gateway lets you to manage your endpoints at scale by providing a secure communications path for:

- Agent authentication and authorization
- Agent licensing
- Directing Recast actions to Agents
- Extending Agent connectivity to the Internet
- Connecting Agents with other Recast components

Multiple Agent Gateways can be added, meaning that there's no limit to the number of Agents that can connect to your Recast Management Server. Internet-connected devices that are not on your local network can connect to the Agent Gateway, allowing you to run Recast actions against them, without the need for a Cloud Management Gateway (CMG).

**NOTE:** One Agent Gateway is required for every 20K Recast Agents deployed.

### View Agent Gateways

The **Recast Agent Gateways** page in RMS displays details related to your Agent Gateways. By default, the one Agent Gateway added automatically during Recast Management Server installation is listed.

**NOTE:** You can view the Agent Gateway to which a specific Agent is connected on the [Agents](#) page.

#### Recast Agent Gateways

Computer Name	Connected	Version	Authorized	Actions
RMS-01	✓	5.9.2502.2110	✓	 
RMS-02	✗		✓	 

1 - 2 of 2 items

Recast Agent Gateway details and actions:

- **Computer Name**
- **Connected:** Shows whether the Agent Gateway is connected to your Recast Management Server.

**NOTE:** Recast Agents must enroll with the Recast Management Server before they can communicate with an Agent Gateway and be used to run actions. See [Deploy Recast Agents](#).

- **Version:** Agent Gateway software version
- **Authorized:** Shows whether an agent gateway is authorized to connect to your Recast Management Server.
- **Actions**
  - **Edit** Agent Gateway details or authorize an Agent Gateway. To manually authorize an Agent Gateway, click the Edit icon to the right of the Agent to authorize. In the **Edit** window, enable the **Authorized** checkbox and click **Update**.
  - **Delete** an Agent Gateway by clicking the Delete icon to the right of an Agent Gateway and confirming the deletion.

### Install an Agent Gateway

# Recast

A single Agent Gateway is automatically deployed and authorized when you install Recast Management Server. You can also install additional Agent Gateways, to accommodate all of your Recast Agents. Each Agent Gateway must be installed on a different server.


## Run the Agent Gateway Installer

After downloading the Recast Agent Gateway software from the [Recast Customer Portal](#), run the installer and follow its prompts.

### IIS

To configure IIS:

1. On the **IIS Configuration** page, specify the **Server Name** in FQDN format (server.domain.local).
2. Set the **IIS Port**. The default IIS Port is **TCP 444**, to prevent conflicts when Recast Management Server is installed on Configuration Manager servers. The IIS Port can be changed to 443, or any open TCP port, to suit your environment.



Recast Agent Gateway - Setup

IIS Configuration

Server Name: GWSEVER


IIS Port: 444

Previous Next Cancel

### Certificates

To configure a certificate:

On the **Certificate Configuration** page, we recommend that you **Use an Existing IIS Certificate** issued by a trusted Certificate Authority (CA). If you choose to **Generate a Self-Signed Certificate**, you must [import the Recast Management Server self-signed certificate to the Trusted Root Certificate Authorities store](#) on devices running Right Click Tools, Recast Agent, or Recast Proxy.



Recast Agent Gateway - Setup

Certificate Configuration

Generate Self-Signed Certificate

Use Existing IIS Certificate

Previous Next Cancel

CERTIFICATE NOTES:


# Recast

- The certificate subject name (or a subject alternative name) should match the server name in the URL that Right Click Tools and Recast Proxies are pointed toward.
- Right Click Tools will prompt for any untrusted certificates and add them to an allowed list.
- The certificate can be changed later by editing the Binding in IIS Manager.

## Recast Management Server Connection

To test the Agent Gateway's connection to your Recast Management Server:

1. On the **Recast Management Server Configuration** page, click **Test Connection**.



2. After a successful connection test, click **Install**.
3. When the installation completes, click **Finish** to close the installer.

## Verify Agent Gateway Installation

In the Recast Management Server interface, navigate to **Administration > Agent Gateways** and check that the new Agent Gateway is connected and authorized. If you've installed an Agent Gateway on a separate server, you may need to [manually authorize it in RMS](#).

For information on the hardware needed for Agent Gateway servers, see [Recast Management Server System Requirements](#).

To learn more about installing your Recast Management Server with an additional Gateway, see [Network Architecture: RMS with Standalone Agent Gateway](#).

The Agent Gateway SQLite file is located at `C:\Users\Recast Agent Gateway\AppData\Roaming\Recast Software\Recast Agent Gateway`

---

## Connect an Agent Gateway to the Internet

You can extend Recast Agent connectivity to devices that are not on your local network by publishing Recast Agent Gateway to the Internet. One method of publishing Agent Gateway to the Internet is to use the Microsoft Entra Application Proxy service. You can find App Proxy requirements and more information in this [Microsoft Entra ID Tutorial](#).

For more detail about this configuration of Recast Software components, see [Network Architecture: RMS with Standalone](#)

# Recast

Agent Gateway.

## Prerequisites


You must have an additional [Agent Gateway](#) installed on a separate server.

- This server must be Internet-connected and able to communicate with your Recast Management Server.
- If you're having issues with a self-signed certificate, you can use an http connection by adding an http connection type under [Internet Information Services \(IIS\) Manager > Sites > Bindings](#). For details, see [How to add binding information to a site](#).

## Connect the Agent Gateway to the Internet

To connect an Agent Gateway to the Internet using the Azure App Proxy service:

1. In the Microsoft Azure portal, under [Enterprise Applications](#), click **New application**.
2. Click **Create your own application**.
3. In the **Create your own application** panel, enter **Recast Agent Gateway** as the name of the application.
4. Select **Configure Application Proxy for secure remote access to an on-premises application**.
5. Click **Create**.



5. Click **Download Application Proxy Connector** then click **Accept terms & Download**.
6. After installing the Application Proxy Connector on your Agent Gateway server, click **I've finished the installation**.
7. Configure Application Proxy settings on the Basic tab:
  - **Name:** Recast Agent Gateway
  - **Internal Url:**
    - Your Agent Gateway server address and port
    - If you're having issues with a self-signed certificate, use http
  - **External Url:** Address to set as the Gateway address when deploying Recast Agents
  - **Pre Authentication:** Select **Passthrough**

## Deploy Recast Agent to the Agent Gateway

You can now [deploy the Recast Agent application](#) and connect it to the Internet-connected Agent Gateway. The App

# Recast

Proxy Agent Gateway port is always 443.

Example:

```
msiexec.exe /i "Recast Agent.msi" /qn /norestart RCTENTERPRISESERVER="https://RMS.RecastDomain.com:444"  
AGENTGATEWAY="https://recastgw-tenant.msapproxy.net:443"
```

NOTE: Installing Recast Agent for the first time requires a Recast Management Server connection.

---

## Authorize an Agent Gateway

When you install an Agent Gateway on a separate server, you'll need to manually authorize it in the Recast Management Server interface.

To manually authorize an Agent Gateway:

1. On the **Recast Agent Gateway** page, click the Edit icon to the right of the agent you want to authorize.
2. In the **Edit** window, enable the **Authorized** checkbox and click **Update**.

