Automation

Last Modified on 10.16.25

Use Builder's templates (or create your own) to run custom actions and workflows.

Recast Builder is an automation engine that allows you to customize Recast actions. Builder can be used with any of Recast's pre-built actions, or you can build your own tools using different Right Click Tools, PowerShell scripts, Registry Edits, WMI Calls, and more. Builder actions can then be saved, shared using role-based permissions, and run using Recast Runner.


Recast Builder is available in a number of Configuration Manager console locations. To open the Builder interface, right click in the console and navigate to Recast Automation > Recast Builder.

For Recast Builder webinars and video tutorials, see the Automation playlist on our YouTube channel.

To explore a shared library of Recast Builder actions and workflows, see our Community Recast Automation Repository. Learn more

Builder Interface Layout

The Recast Builder interface consists of a central canvas surrounded by three panels.



On the left

A. My Right Click Tools panel: Displays the icons for adding a new action, saving the current action, and deleting saved actions. Saved actions and pre-built templates are accessible from the panel according to where they were created in the Configuration Manager console. If, for example, Recast Builder is accessed from Devices, tools for editing devices will be displayed.

On the right

B. Recast Actions panel: This searchable list displays hundreds of available actions by category. For a full list of available actions, see the Recast Actions Catalog.

In the center

- C. Canvas: Drag and drop your saved Right Click Tools, pre-built templates, and Recast Actions onto this area to work with them. The Start Node represents the object selected when running the action, such as a device or user.
- D. Viewfinder: Use this box to move around the canvas and to adjust settings including the zoom level, centering and fill.

At the bottom

E. Properties and parameters: Different sections appear at the bottom of the interface depending on what is selected on the canvas.

Action Properties: Configure View, Name, Display and Action Type options for your custom tools. See Configure Action Properties.

Target Input Parameters: Map a parameter to a constant value or to a specific property or step. See Map Target Input Parameters.

Custom Input Parameters: Provide users with input options before an action runs. Common uses include choosing a collection to which a device will be added, choosing whether to force a full inventory cycle upon completion, and having an admin input a PowerShell script.

See Set Custom Input Parameters.

Conditional Responses: Set conditional responses to skip actions based on the results of previous actions. See Set Conditional Responses.

Create a New Recast Action

To create a new custom tool in the My Right Click Tools list, click the New Action button (+ sign).



Use a Pre-Built Workflow

Recast offers a set of pre-built actions to get you started with Builder. These workflows are made up of a sequence of actions, and can be used as-is or as a starting point for creating your own custom Right Click Tools. For a description of the tasks included in each pre-built sequence of actions, see Recast Builder Actions.

Pre-built actions are listed in the My Right Click Tools panel. The Builder Actions displayed will vary depending on where you've opened Builder in your Configuration Manager console. For example, when Builder is accessed from Users, the templates that include user management actions will appear.



Drag-and-drop the templates onto the canvas to view and/or edit the actions they include. Pre-built actions often require some configuration in Builder. For instructions, see Configure Builder Actions.


In addition to the pre-built actions available within Builder, you'll also find a growing collection of Recast actions and workflows in our Community Recast Automation Repository. You can import any of the templates from this shared library into Builder.

Add Recast Actions

You can add any of the actions listed in the Recast Actions panel to create an automated workflow. For a list of all the available actions, see the Recast Actions Catalog.

To add actions to an automation sequence:


- 1. Use the Recast Actions search box or drill-down menu to select the desired actions.
- 2. Drag-and-drop each action onto the canvas area.



3. Order the sequence of actions from the Start Node to the first action by selecting the circle edge and dragging it to the first box.



Builder will auto-select the Edge arrow in blue and populate the item properties in the Selected Edge section. Setting parameters will tell Configuration Manager which properties to change on the targeted object.



Configure Action Properties

Choose Action Properties to determine the design and configuration of a Recast Builder action.

To choose action properties:


- 1. On the canvas, click the Start Node (the object the user will click on to run the tool).
- 2. Under Action Properties, specify the View, Name, Display and Action Type, which are described below.

View

The **View** field determines how the results of a Right Click Tools Builder tool will display. View options do not affect the technical operation of Right Click Tools Builder tools — they only affect how results are displayed.


View Options:

- Single Grid Results
- Two Grid Results
- Tabbed Results: Shows a result for each step of the tool



Name


Name sets the name of the Recast Builder tool. After entering a new tool name, click the Save icon in the My Right Click Tools panel.



Display

Display sets the Configuration Manager object that the Right Click Tools Builder tool is run against. Options differ according to the selected **Action Type**.

Example: For a tool run against a device, Computer Name would be an appropriate display option.




Action Type

The Action Type sets the properties on which the tool will take action.

Action Type Options:

- Generic: For all Right Click Tools Builder Tools acting on functions not related to users or devices.
- Device (with or without resource ID): For tools acting on devices. These tools will be available anywhere Right Click Tools device tools are available. The Resource ID is Configuration Manager's unique identifier for a computer object.
- User (with or without Resource ID): for tools acting on users. These tools will be available anywhere Right Click Tools user tools are available. The Resource ID is Configuration Manager's unique identifier for a user object.



Set Custom Input Parameters

Input Parameters can be used to offer administrators and end users with options before an action is run.

Examples of custom inputs:

- Choosing a collection to which a device will be added.
- Choosing whether or not to force a full inventory cycle upon completion.
- Having an admin input a PowerShell script.


To add an input parameter:

Under Custom Input Parameters, select an option from the drop-down list and click Add.


Parameter Options

- Boolean: Prompts the user running the action with an option to check or uncheck the parameter mapped to the Boolean.
- DateTime: Prompts the user running the action with an option to select the date and time.
- Integer: Prompts the user running the action with an option to set an integer value. You also have the option to set a default, minimum, and maximum value.
- TimeSpan: Prompts the user running the action with an option to set a length of time. A default value can be set, if
- String: Provides two options -List or Textbox. This will prompt the user running the action to select or input a string.

List



Textbox



To remove an input parameter:

Under Custom Input Parameters, select a listed item and click Remove.

Map Target Input Parameters

Parameters can be mapped to a constant value or a specific property or step. Constant values must be specified, whereas Parameter Mapping values can be pulled from any step of the existing tool to any property of the action being taken. This should be done for every parameter appropriate for the actions you are trying to take.

- Use a Constant value to hard code a value.
- Use Parameter Mapping for actions where you need to pull inputs from the user or where the properties of the object should change.


To map to a constant value:

Under Target Input Parameters, select Constant.

Selected Edge Target Input Parameter	s	Condition	
SAM Account Name	Constant	V	Add Condition
Domain	Constant		
Group	Parameter Mapping		
		Output Condition	Value
	Remove Edge		
Selected Item Properties			

To map to a property or step:

Under Target Input Parameters, select Parameter Mapping, then select the Node and the Parameter from the drop-down lists.




Set Conditional Responses

Right Click Tools Builder lets you set conditional responses, allowing you to skip actions based on the results from previous actions. If the conditions are true, Recast Runner will execute the next step according to the specified workflow. If not, the next step (and any subsequent step in the chain) will be skipped.

Logical term options: And, Or, Less Than, Less Than or Equal To, Equal To, Greater Than, Greater Than or Equal To


To add a conditional response:

- 1. On the canvas, click on the edge (arrow) that connects the two actions between which you want to add a condition.
- 2. In the Condition section, click the New Condition icon (+ sign) and select a logical term from the drop-down list.



3. Associate the condition with a specific Output and/or input Value.

In this example, an "Equal To" condition has been set from the Computer Name to the name of device "XYZ".



Recast Builder Actions

Recast Builder Actions can help you quickly automate a workflow in your environment. These pre-built sequences of actions are designed to get you started using Recast Builder, introduce you to some of the automation features available in Builder, and help you start making tools on your own.

As of v5.1.2305.507, pre-built actions can be accessed from within Recast Builder, removing the need to import them into the interface. These actions will only appear in Builder, upon upgrade or with a fresh install, for deployments that do not already have existing Builder actions in place. To learn more, see Configure Recast Builder Actions.

Disclaimer: These Builder actions are provided on the basis that they can be edited, changed, and shared, but not sold. While every available effort has been made to be sure they work well and do what was intended, we can't anticipate the requirements of every conceivable Configuration Manager environment, so download/use at your own risk — no guarantees of function, support, or that they won't break something. As with everything, test first.

All Client Policies

This Builder action runs through all the Configuration Manager's client policies. This is great for new or recently re-built computers to force them to check into Configuration Manager.

This tool completes the following steps:

- Ping computer
- Machine Policy Retrieval and Evaluation Cycle
- Discovery Data Collection Cycle
- Hardware Inventory Cycle
- Software Inventory Cycle
- Send Unsent State Messages Cycle
- Software Updates Scan Cycle
- Application Deployment Evaluation Cycle
- State Message Cache Cleanup
- Windows Installer Source List Update Cycle
- Software Inventory Cycle
- File Collection Cycle
- Software Updates Deployment Evaluation Cycle

For v5 Releases: Now available in Builder, All Client Policies 5.xml @

Add an AD User to an AD Group

This Builder action lets you add an AD user to an AD group from a list of groups.

For v5 Releases: Now available in Builder, Add To Group 5.xml

For instructions on setting up this template in Builder, see Configure Starter Pack Templates in Recast Builder.

BitLocker Recovery Password from Device

This Builder action grabs the BitLocker Recovery Password from any drive on a device. This uses a custom input parameter to allow users to choose what drive they want to grab the recovery password from.

This tool completes the following step:

• Get Recovery Password From Device

For v5 Releases: Now available in Builder, BitLocker Recovery Password 5.xml @

Compare Two Users' AD Groups

This Builder action lets you compare the group memberships of two AD users. This action is particularly useful if, for example, you have a new team member and want to compare their group memberships to those of an existing team member.

This tool completes the following steps:

- Gets AD group membership for a selected user
- Prompts you to enter the AD username that you'd like to compare against the selected user
- Shows you group memberships for both users in tabbed results

For v5 Releases: Now available in Builder, Compare AD Groups 5.xml

User Account Retire Protocol

This Builder action automates a common task — taking steps when a person leaves an organization to secure their account credentials and prepare the account for retirement. It's easily adaptable to other user-based tasks as well, and is a nice jumping-off point for Recast Builder.

This tool completes the following steps:

- Prompts the admin running the tool to input a new password for the account
- Resets the password for the account to this password
- Disables the account
- Moves the account to a new OU

In the Target Input Parameters panel, you must specify a valid OU in your environment as a Constant value.

Format Example: OU=RecastUsers,DC=demo,DC=recastsoftware,DC=com

For v5 Releases: Now available in Builder, User Account Retire Protocol 5.xml @

For instructions on setting up this template in Builder, see Configure Recast Builder Actions.

Reboot if Pending Restart Exists

This Builder action allows you to force a restart on systems that have a pending reboot scheduled, without requiring you to query for pending reboot data in advance. It's a friendly way to help your end users who hate to restart stay updated and compliant without requiring any personal intervention.

This tool completes the following steps:

- Ping Computer
- If Ping is successful, Check System Information Collection for Pending Restart Information
- If Pending Restart Exists, force a Reboot with a 5-minute timer and a user pop-up message: "Your computer needs to restart, please save and close in the next 5 minutes."

For v5 Releases: Now available in Builder, Reboot If Pending Restart Exists 5.xml @

Video Overview

Re-Enroll Agent

There are times when a Recast Agent attempts to connect to a Recast Management Server, but is unable. You'll see a warning in the Recast Management Server telling you that there is an Agent that is trying to connect, but it is not approved. This occurs most often if you delete the Agent from the Recast Management Server manually. Because the Agent information is deleted, there is no way to approve this Agent.

To resolve the problem, use this Builder action to re-enroll the Recast Agent.

The tool completes the following steps:

• Deletes the agent.sqlite file located in this folder:

Version 5.x Recast Agent: C:\ProgramData\Recast Software\Recast Agent

Version 4.x Recast Agent: C:\Windows\System32\config\systemprofile\AppData\Roaming\Recast Software\Recast Agent

• Restarts the Recast Agent service

For v5 Releases: Now available in Builder

For v4 Releases: Re-Enroll Agent.xml

Grant Remote Access

This Builder action is used to grant a specific AD user remote access to a device by adding the user to the local "Remote Desktop Users" group on the device.

The tool completes the following steps:

- Asks for the AD Username
- Adds the AD Username entered to the "Remote Desktop Users" local group.

For v5 Releases: Now available in Builder, Grant Remote Access 5.xml @

For instructions on setting up this template in Builder, see Configure Recast Builder Actions.

Configure Pre-Built Templates

As of Recast Software Version 5.1.2305.507, pre-built Recast templates can be accessed from withinRecast Builder, eliminating the need to import them from the Recast Builder Actions page. These templates appear upon upgrade or with a fresh install for deployments that do not already have existing Builder templates in place.

For a description of the actions included in each pre-built template, see Recast Builder Actions.

For more information on configuring properties, parameters, and conditions, see the Recast Builder Overview.

You'll find pre-built Recast actions listed in the My Right Click Tools panel. Drag-and-drop them on to the canvas to view the sequence of included steps and edit their properties and parameters.

Some pre-built templates require a bit of configuration in Recast Builder before they can be run.

User Account Retire Protocol

For this Recast action, the Start Node represents the user account selected in Configuration Manager before running the action. The edges (aka the arrows) are preconfigured to link the Start Node to the Reset Password, Disable Account and Move Account to Container actions.

To configure the action:

1. Select the Start Node on the canvas.

Under Action Properties, view or edit the default settings and name the tool:

- View: Tabbed Results
- Name: For example, User Account Retire Protocol
- Display: User NameAction Type: User

Under Custom Input Parameters, view or edit the default settings:

- Display Name: Input a New Password
- Variable Name: TextBoxValue
- Minimum Length: 1Maximum Length: 20
- 2. Select the edge linking the Disable Account and Move Account to Container actions.

Under Target Input Parameters, update the ADPath as a Constant value.

ADPath Format Example: ADPath=RecastUsers,DC=demo,DC=recastsoftware,DC=com

NOTE: The ADPath is case sensitive.

Video Overview

Recast Actions Catalog

A list of all the actions available from the Recast Actions panel in the Builder interface.

Plugin	Action

Plugin	Action
Active Directory	Add Account to Group
	Delete Account
	Disable Account
	Enable Account
	Get Account Group Membership: Returns all groups for an AD account.
	Get AD Computer
	Get AD Computers: Returns all devices for an AD domain.
	Get AD Computers BitLocker Status
	Get AD Computers in Group: Returns all nested devices in an AD group.
	Get AD Computer with LAPS Data
	Get AD Container by Distinguished Name
	Get AD Container by Object Guid
	Get AD Container by Object Guide Core
	Get AD Groups: Returns all groups for an AD domain.
	Get AD Groups in Group
	Get AD OUs
	Get AD User
	Get AD Users: Returns all users for an AD domain.
	Get Ad Users in Group
	Get BitLocker Recovery Data
	Get Domain
	Get Group Members
	Get Group Memberships: Returns all groups for the user or device from AD, including
	nested groups.
	Get Parent OUs: Returns all parent Organizational Units.
	Get Primary Group for Account
	Is Account Enabled
	Move Account to Container
	Remove Account from Group
	Reset Password
	Search AD Computers
	Search AD Groups
	Search AD Users
	Search OUs
	Search Principal
	Set LAPS Password Expiration
	Split Computer Name: May be required when using the Get AD Computer action
	Unlock Account

Plugin	Action
Administration	Add Permission to Role Add Nole Add User Add User to Role Change Enrollment Settings Change Setting Delete Role Delete Role Delete Route Delete User Get Admin Trend List Get All Permissions Get All Settings: Returns all names and current values listed on the RMS Settings page. Get Enrollment Settings Get Execution History: Returns audit log information. Get Permissions Details for User Get Permissions for Role Get Permissions for User Get Roles: Returns all user roles in RMS. Get Roles for User Get Trend Get Trend Get Trend List Get Trends by Type Get Users: Returns all users in RMS. Remove Permission from Role Remove User from Role Rename Role
Azure Active Directory (Entra ID)	Get Device Group Memberships Get Domain Get Group Memberships: Returns all groups for the user or device from Graph API, including nested groups. Search Principal Test New Service Connection Test Service Connection
BitLocker	Add Numerical Password Key Protector Add Passphrase Key Protector And Protectors and Encrypt Add TPM and PIN Key Protector Add TPM and Startup Key Key Protector Add TPM Key Protector Backup Key Protector to Active Directory Backup Key Protector to Azure Active Directory Decrypt Volume Encrypt Volume
Builder Action	Concatenate Strings List Actions List Actions in Category List Actions with Type Run Saved Action: Runs a Builder Action and returns results. Sleep Start Node

Plugin	Action

Plugin	Action
ConfigMgr Client	Advanced Client Information
	Application Deployment Evaluation Cycle: Initiates this cycle on a ConfigMgr client.
	Boundaries
	Boundary Groups
	Change Cache Size
	Clear Cache: Deletes all content in the ConfigMgr client cache.
	Client Cache General Information: Returns a summary of client cache information.
	Client Cache Content: Returns all content details in the cache.
	Execution History
	Installed Client Components
	Deployed Applications: Returns all ConfigMgr-deployed applications from the client.
	Deployments: Returns all ConfigMgr programs and task sequence deployments from the client.
	Discovery Data Collection Cycle: Initiates this cycle on a ConfigMgr client. Evaluate Configuration Baseline
	File Collection Cycle
	General Client Information: Returns ConfigMgr client information
	Get Boundary Information
	Get Client Information Cache Data: Returns cache usage summary for a ConfigMgr
	client.
	Get Configuration Baselines: Returns all deployed ConfigMgr baselines from a client.
	Get Deployed Programs: Returns all ConfigMgr-deployed programs from the client.
	Get Deployed Task Sequences: Returns all ConfigMgr task sequences deployed to a
	device.
	Get Device ID
	Get Service Windows
	Get User Policy Endpoint
	Hardware Inventory Cycle: Initiates this cycle on a ConfigMgr client.
	Install Application
	Install Application or Program: Initiates installation of a ConfigMgr application or
	program on a device.
	Install Program
	Install Software Updates
	Install Software Updates by ID
	Install User Application
	Machine Policy Retrieval and Evaluation Cycle: Initiates this cycle on a ConfigMgr client.
	Missing Software Updates: Returns all missing software updates currently deployed to
	a device.
	Package Information
	Refresh Updates Compliance State
	Remove Items from Cache
	Repair Client: Initiates ConfigMgr client repair process.
	Rerun Deployment: Initiates deployment execution of task sequences or package
	programs on the ConfigMgr client.
	Restart SMS Agent
	Run Client Check
	Run Client Action
	Send ConfigMgr Client Toast Notification
	Send Unsent State Messages: Sends pending state message for a ConfigMgr client.
	Software Inventory Cycle: Initiates this cycle on a ConfigMgr client.
	Software Metering Usage Report Cycle
	Software Updates Deployment Evaluation Cycle: Initiates this cycle on a ConfigMgr
	client.

	Software Updates Scan Cycle
Blugigmgr Server	AGI Computer Names to Collection
	Add Device Resource ID to Collection
	Add Content to Distribution Point
	Add Content to Distribution Point Group
	Add Devices to Collection: Adds devices to a collection, based on a specific or
	wildcard search of computer names.
	Add Devices to Collection by Resource ID
	Add Item to Scope
	Add User Resource ID to Collection
	Add Users to Collection
	Approve or Deny Request
	Content Details: Returns content information and summary for distribution points.
	Create Query
	Delete Device
	Delete Devices
	Delete User
	Get Accounts
	Get Active Alerts
	Get Active Directory Forests
	Get Administrative Users
	Get Alert Subscriptions
	Get All Alerts
	Get All Collections
	Get All Content Status
	Get All Deployment Types: Returns all application deployment types in ConfigMgr.
	Get All Device Collections
	Get All Device Collections by Collections
	Get All Devices
	Get All Devices in OU
	Get All Distributed Content: Returns all distributed content in ConfigMgr.
	Get All Software Updates
	Get All User Collections
	Get All Users
	Get Application by ID
	Get Application Revisions
	Get Applications
	Get Approval Requests
	Get Asset Intelligence Catalog
	Get Asset Intelligence Hardware Requirements
	Get Asset Intelligence Inventoried Software
	Get Automatic Deployment Rules
	Get Baseboard Information
	Get Boot Images
	Get Boundaries
	Get Boundary Groups
	Get Category Instance by ID
	Get Category instance by iD Get Certificates
	Get Chassis Information
	Get Client Operations
	Get Client Settings
	Get Collection Folder Information
	Get Collections for Device
	Get Collections for User
	Get Collection Variables for Device
	Get Comanaged Device Workloads by Collection: Given a Collection ID, returns

devices and workloads comanaged in ConfigMgr and Intune. Get Comanaged Workloads: Given a Resource ID, the action returns workloads that Plugin are being comanaged in Configuration Manager and Intune. Get Compliant Update Statuses Get Component Status Get Computers Without LAPS Client: Returns all devices without a legacy Microsoft LAPS client. Get Computers with x64 LAPS Client: Returns all devices with a 64-bit legacy Microsoft LAPS client. Get Computers with x86 LAPS Client: Returns all devices with a 32-bit legacy Microsoft LAPS client. Get Computer System Information Get Computer Warranty Get Configuration Baselines Get Configuration Items **Get Conflicting Records** Get Content Status: Returns content information and summary of distribution status. Get Deployed Applications for User Get Deployment Packages Get Deployments Get Deployment Types for Application Get Device Collection Folders Get Device Collection Information for Device: Returns information about all collections for a device. Get Device Collection Members: Returns all devices in a collection. Get Device Collections in Folder Get Device Count Get Devices by Creation Date Get Devices by MAC Address Get Devices by BIOS GUID Get Devices by ME ID: Given one or more Microsoft Entra ID GUIDs, a Site Code and a SMS Provider, returns the domain name for a device from ConfigMgr. Get Discovery Methods Get Distributed Software Updates: Returns all software updates distributed in a ConfigMgr site. Get Distribution Point Configuration Status Get Distribution Point Content Get Distribution Point Groups Get Distribution Point Group Status Get Distribution Point Group Status for Package: Returns all distribution point groups for a piece of content. Get Distribution Points in Distribution Point Group Get Distribution Point Status for Package: Returns all distribution points for a piece of content. Get Distribution Point Groups with Members Get Distribution Point Group Task Sequence Content Get Driver Packages Get Drivers Get Endpoint Protection Antimalware Policies Get Endpoint Protection Firewall Policies Get Failed Content on Distribution Point Get Global Conditions Get Installed Software Updates Get Machines with ConfigMgr BitLocker Management Keys: Returns all devices with BitLocker keys in ConfigMgr. Get Malware Detected Get Manufacturer Counts

	Get Migration Jobs
	Get Non-Compliant Update Statuses
Plugin	Get Object Container Items
	Get Operating System Images
	Get Operating System Installers
	Get Packages
	Get Power Configurations for Computer
	Get Queries
	Get Recent Devices Scanned
	Get Required Software Updates
	Get Scope Memberships
	Get Security Roles
	Get Security Scopes
	Get Servers and Site System Roles
	Get Service Windows for Computer
	Get Sites
	Get Site Status: Returns all site systems statuses in ConfigMgr.
	Get Software Metering Rules
	Get Software Update Groups: Returns all software update groups in ConfigMgr.
	Get Software Updates in Group
	Get Status Message Queries
	Get System BIOS Information
	Get System Console Usage Data
	Get System Firmware Status
	Get System Operating System Information
	Get Systems BitLocker Encryption Status: Returns the BitLocker encryption status for
	devices in ConfigMgr.
	Get Task Sequence Content
	Get Task Sequences
	Get Unknown Devices
	Get User Collection Folders
	Get User Collection Members
	Get User Collections in Folder
	Get User Devices
	Get User Devices by User Name
	Get User State Migrations
	Get Virtual Hard Disks
	Get Warranty Information: Retrieves and updates warranty data in ConfigMgr for a
	collection of devices.
	Install Application
	Redistribute Content to Distribution Point: Initiates redistribution of content to a
	distribution point.
	Redistribute Content to Distribution Point Group
	Remove Content from Distribution Point: Initiates removal of content from a
	distribution point.
	Remove Content from Distribution Point Group
	Remove Devices from Collection
	Remove Devices from Collection by Resource ID
	Remove Item from Security Scope
	Remove Users from Collection
	Remove Users from Collection by Resource ID
	Run Client Operation
	Run Configuration Manager WQL Query
	Run ConfigMgr Script on Devices
	Run Recast Action: Runs a Recast Action on the Fast Channel and returns results.
	Run Status Message Query
	Run WQL Query
	Hall Wat adding

Plugin	Save Query Start CM Site Backup
	Validate Content on Distribution Point Group: Initiates ConfigMgr validation for content on a distribution point. Wake on LAN: Sends a Wake on LAN packet to a device. Wake on LAN Fast Channel
Email	Send Email via SMTP
Endpoint Insights	Open Recast Endpoint Insights Report Viewer
Filesystem	Append Text to File Copy File Copy Folder Create Folder Delete File Delete Folder Move File Move Folder Replace Text in File Set Owner on File Set Owner on Folder Write Text to File
Installed Software	List Software: Returns all software in Add/Remove Program on a device. Uninstall Software
Kiosk Manager	Applied Profile Status Apply Profile: Applies a Kiosk Manager profile to a device. List Profiles: Returns all saved Kiosk profiles. Prepare Profile Rollback Profile
MBAM	Get Machines with MBAM Keys Get Machines with MBAM Keys v2 Get MBAM Compliance Get MBAM Compliance for All Machines Get Recovery Keys for Device Get TPM Hash Get TPM Hash for User
Network	Ping Computer: Returns a response to an Internet Control Message Protocol (ICMP) echo request from a device.
PowerShell	Run PowerShell Script Block
Registry	Add Permission Create Subkey Delete Subkey Delete Value Get Value List Hives List Subkeys List Values Remove Permission Rename Value Set Owner Set Value

Plugin	Action
System Center Endpoint Protection	Add Defender Exclusion Full SCEP Scan Gather SCEP Logs Get Defender Exclusions Get Defender Status Start Defender Scan Update SCEP Definitions
Scheduler	Cancel Action
Services	Change Login Change Start Mode List Services: Returns all services on a device. Restart Service Start Service Stop Service
System Information	Add Local Group Member Cancel Shutdown Remove Local Group Member Delete Profile: Deletes a Windows user profile from a device. Get All Local Group Members Get Battery Information Get Drivers Get General Information: Returns hardware and operating system information for a device. Get Logged in Users: Returns all users currently logged into a device. Get Running Processes Get Updates: Returns all software updates installed on a device. Get User Profiles: Returns all users currently logged into a device. Get User Sessions: Returns all users currently logged into a device. Group Policy Update: Initiates a group policy update on a device. Kill Process Log Off All Users Log Off User Session Reset BitLocker Recovery Password Schedule Shutdown Send Message to All Users Send Message to User Session Send Recast Toast Notification Shut Down Computer: Initiates shutdown and restart of a device. Shut Down Computer with Prompt System Information Collection
Task Scheduler	Delete Task Get Task Results Get Task Results for Date List Tasks Schedule Task Schedule Task Daily Schedule Task Monthly by Day Schedule Task Monthly by Occurrence Schedule Task Weekly Start Task by ID Start Task by Name

Add File Exclusions
Add Registry Exclusions
Apply Profile
Commit File Deletions
Commit Files
Commit Registry Deletion
Commit Registry Values
Configure Unified Write Filter
Delete Profile
Disable Bind by Drive Letter
Disable Servicing
Disable Unified Write Filter
Enable Bind by Drive Letter
Enable Servicing
Enable Unified Write Filter
Find File Exclusion
List File Exclusions
Get Overlay Configuration
List Registry Exclusions
Get Unified Write Filter Feature Status
Get Unified Write Filter Status
Install Unified Write Filter
List Profiles
Protect All Volumes
Protect Volume
Remove All File Exclusions
Remove All Registry Exclusions
Remove File Exclusions
Remove Registry Exclusions
Remove Unified Write Filter
Reset Unified Write Filter Settings
Restart System
Save Profile
Set Maximum Overlay Size
Set Overlay Critical Threshold
Set Overlay Type
Set Overlay Warning Threshold
Shut Down System
Unprotect Volume
Update Windows
Use Disk Overlay
Use RAM Overlay
Volume is Protected

Plugin	Action
Windows Security	Clear TPM Enable Credential Guard Settings Enable System Guard Secure Launch Enable TPM Auto Provisioning Enable Virtualization Based Security Get All Virtualization Based Security Settings Get TPM Status Get UEFI Secure Boot Status Get Virtualization Based Security Settings Get Windows Firewall Profiles Get Windows Firewall Rules Provision TPM
Windows Task Scheduler	Delete Task List Tasks Run Task Schedule Task
Windows Update Agent	Get Updates: Returns missing software updates for a given computer. Download and Install Updates: Downloads and installs all missing software updates on a comanaged device. Download and Install Select Updates: Downloads and installs selected missing software updates on a comanaged device.
Windows Management Instrumentation (WMI)	List Classes List Class Methods List Instance Methods List Instances List Namespaces Run Class Method Run Instance Method Run WQL Query

Import/Export Builder Actions

Export Actions from Builder

Exporting Builder actions allows you to save them as XML files that can then be imported into another system.

To export Builder actions:

- 1. In the Recast Builder interface, right-click in the whitespace below the saved actions in the My Right Click Tools panel.
- 2. Select Export.

Import Actions into Builder

You can import pre-defined templates or your own custom actions into Builder.

To import actions into Builder:

1. Open Recast Builder from the location you wish to be able to run the tool from later (for example, if importing a device tool template, access Builder from **Devices**).

- 2. In the My Right Click Tools panel to the far left, right-click in the whitespace below the saved actions.
- 3. Select Import.
- 4. Navigate to and open the XML file for the action you wish to import.

The saved action will appear in your My Right Click Tools panel.

Builder Suggestions

Is there an action that you wish you had in Recast Builder?

Yes? Awesome! Feel free to submit a Builder suggestion. We can't guarantee that we'll be able to create every Builder action requested, but we'll do our best to create the action for you, if possible.

Email your Builder suggestions directly to support@recastsoftware.com.

Disclaimer: Builder actions and pre-built workflows are provided on the basis that they can be edited, changed, and shared, but not sold. While every available effort has been made to be sure they work well and do what was intended, we can't anticipate the requirements of every conceivable Configuration Manager environment, so download/use at your own risk—no guarantees of function, support, or that they won't break something. As with everything, test first.

Recast Runner

Recast Runner executes actions created with Recast Builder. Builder actions can only be run with the user account accessing the Configuration Manager console or by routing over the Recast Proxy service account.

To execute a Builder Action with Recast Runner:

- ${\tt 1. Right-click\ in\ your\ Configuration\ Manager\ console\ and\ select} \ \textbf{Recast\ Automation\ > Recast\ Runner}.$
- 2. In the RCT Runner Run Action dialog, select an action and click Next.
- 3. Choose to run the action immediately or according to a schedule and clickFinish.