Recast

Device Collections

Last Modified on 2026-09-28

With the help of device collections, you can organize devices within a network based on your own criteria and configure and deliver packages or deployments simultaneously on multiple devices across a network.

Device collections can be accessed from **Manage** > **Identities** or **Devices** > **Memberships**.

Two types of collections are available:

- Static device collections
- Dynamic device collections

If you need a dynamical grouping which entails attributes other than *Platform* and *Device*, we recommend using the contexts feature. For more information, see Contexts.

The only built-in device collection is the *All devices*.

Selecting multiple table rows

- Adjacent rows: Click on the first row, hold down the Shift key, click on the last row in the range
- Non-adjacent rows: Hold the Ctrl or Cmd key and click on each row you want to select
- Adjacent rows, using only the mouse: Click and hold the left mouse button on the first row, then drag the cursor up or down across the rows to highlight the desired ones

Keep in mind that only devices running an Application Workspace Agent/ a Liquit Workspace Agent can be added to a collection.

The **Type** of a collection (Dynamic, Static) cannot be changed after creation.

Device collections list

This list displays all device collections currently available in the Application Workspace System.

Selecting multiple table rows

- Adjacent rows: Click on the first row, hold down the Shift key, click on the last row in the range
- Non-adjacent rows: Hold the Ctrl or Cmd key and click on each row you want to select
- Adjacent rows, using only the mouse: Click and hold the left mouse button on the first row, then drag the cursor up or down across the rows to highlight the desired ones

Table toolbar

To create a new device collection, click on the **Create** button; to view the details of a device collection or edit it, double-click its entry or select the collection and click the **Edit** button.

From the table toolbar you can also access the **Wake devices** and create personalized views of the list, all of which are described in the following sections.

Recast

Wake devices

If the server is in the same LAN as devices, the **Wake devices** button is able to wake computers that are shutdown or in sleep mode (WoL). If the server is in the cloud, the **Wake devices** button does not function.

Views

Views gives you control on how the table is displayed.
The default view contains all your device collections in alphabetic ascending order, and only a few columns: **Name**, **Type**, and **Built-in**.
You can create your own personalized view of the table, by filtering the device collections or adding/deleting columns and clicking **Save as** in the drop-down menu of **Views**.