Recast

Settings

Last Modified on 2026-11-02

Get-LiquitSetting

This command displays a list of all settings configured for the zone, context, server or device. Alternatively, you can select a specific setting.

Syntax

```
Get-LiquitSetting
   [-LiquitContext <LiquitContext>]
   [<CommonParameters>]

Get-LiquitSetting
   [-Context] <Context>
   [[-ID] <string[]>]
   [-LiquitContext <LiquitContext>]
   [<CommonParameters>]

Get-LiquitSetting
   [-Server] <Server>
   [[-ID] <string[]>]
   [-LiquitContext <LiquitContext>]
   [<CommonParameters>]

Get-LiquitSetting
   [-Device] <Device>
   [[-ID] <string[]>]
   [-LiquitContext <LiquitContext>]
   [<CommonParameters>]

Get-LiquitSetting
   [[-ID] <string[]>]
   [-LiquitContext <LiquitContext>]
   [<CommonParameters>]
```

Examples

This command displays all settings defined within Application Workspace:

```
Get-LiquitSetting
```

This command displays the settings for the background color of the login page:

```
Get-LiquitSetting -id login.background.color
```

For all available settings, see Settings.

Recast

Clear-LiquitSetting

This command resets a setting to its default.

Syntax

```
Clear-LiquitSetting
   [-Setting] <Setting[]>
   [-LiquitContext <LiquitContext>]
   [-WhatIf]
   [-Confirm]
   [<CommonParameters>]

Clear-LiquitSetting
   [-Context] <Context>
   [-ID] <string[]>
   [-LiquitContext <LiquitContext>]
   [-WhatIf]
   [-Confirm]
   [<CommonParameters>]

Clear-LiquitSetting
   [-Server] <Server>
   [-ID] <string[]>
   [-LiquitContext <LiquitContext>]
   [-WhatIf]
   [-Confirm]
   [<CommonParameters>]

Clear-LiquitSetting
   [-Device] <Device>
   [-ID] <string[]>
   [-LiquitContext <LiquitContext>]
   [-WhatIf]
   [-Confirm]
   [<CommonParameters>]

Clear-LiquitSetting
   [-ID] <string[]>
   [-LiquitContext <LiquitContext>]
   [-WhatIf]
   [-Confirm]
   [<CommonParameters>]
```

Example

The following script resets the theme to default:

```
$setting = Get-LiquitSetting -id portal.style
Clear-LiquitSetting -Setting $setting
```

Parameters

Name	Value	Description	Required	Default value

Recast

Name	Value	Description	Required	Default value
Setting	`<Setting[]>`	The setting you want to reset to default.	Yes	
LiquitContext	`<LiquitContext>`	Determines the selected zone.	No	Default

Set-LiquitSetting

This command lets you edit the properties of a scheduled task.

Syntax

```
Set-LiquitSetting
   [-Setting] <Setting[]>
   [[-Value] <Object>]
   [-Force <bool>]
   [-LiquitContext <LiquitContext>]
   [-WhatIf]
   [-Confirm]
   [<CommonParameters>]

Set-LiquitSetting
   [-Context] <Context>
   [-ID] <string[]>
   [[-Value] <Object>]
   [-Force <bool>]
   [-LiquitContext <LiquitContext>]
   [-WhatIf]
   [-Confirm]
   [<CommonParameters>]

Set-LiquitSetting
   [-Server] <Server>
   [-ID] <string[]>
   [[-Value] <Object>]
   [-Force <bool>]
   [-LiquitContext <LiquitContext>]
   [-WhatIf]
   [-Confirm]
   [<CommonParameters>]

Set-LiquitSetting
   [-Device] <Device>
   [-ID] <string[]>
   [[-Value] <Object>]
   [-Force <bool>]
   [-LiquitContext <LiquitContext>]
   [-WhatIf]
   [-Confirm]
   [<CommonParameters>]

Set-LiquitSetting
   [-ID] <string[]>
   [[-Value] <Object>]
   [-Force <bool>]
   [-LiquitContext <LiquitContext>]
   [-WhatIf]
   [-Confirm]
   [<CommonParameters>]
```

Example

The following script forces the theme setting:

```
$setting = Get-LiquitSetting -id portal.style
Set-LiquitSetting -Setting $setting -Force $true
```

Parameters

Recast

Name	Value	Description	Required	Default value
Setting	`<Setting[]>`	The setting you want to edit.	Yes	
Value	`<Object>`	The new value of the setting.	No	
Force	`<bool>`	Whether or not the end user should be blocked from changing the setting.	No	False
LiquitContext	`<LiquitContext>`	Determines the selected zone.	No	Default