View and Edit Collected Inventory Classes

Last Modified on 2026-10-28

The Right Click Tools Insights **Settings** page displays the Default inventory policy, which includes all the classes of inventory data collected for Agent-based devices. The complete list of inventory classes and properties is also available here in the Recast Help Center.

Minimum Right Click Tools Version: 5.12.2609; 5.13.2610 to import user-defined classes


Enable or Disable Collection of Specific Inventory Classes

By default, Insights collects inventory data for all available Recast classes. Insights administrators can choose to customize the information collected by enabling or disabling individual inventory classes or properties. This means you can collect just the details you're interested in and avoid a deluge of data.

To enable/disable an inventory class or attribute:

1. In your Recast Management Server or Recast Cloud, navigate to**Insights** > **Settings**.

2. On the **Inventory Policy** tab, select or deselect classes. You can also expand a section, or all sections, to enable or disable specific properties.



Import a User-Defined Inventory Class

You can add a user-defined inventory class to the Default inventory policy to collect custom inventory data alongside the available Recast inventory classes.

NOTE: For self-hosted instances, there is no limit on custom class counts. For cloud instances, there is a limit of five classes.

To import a user-defined inventory class:

1. In your Recast Management Server or Recast Cloud, navigate to**Insights** > **Settings**.

2. On the **Inventory Policy** tab, click **Import Inventory Class**.

3. Enter a device name and click **Browse** to view the available WMI classes.

4. Choose the classes and/or individual properties you want Insights to collect. Click **Add**.

NOTE: The **Inventory Policy** tab displays your Imported Classes below the collected Recast Classes.

Insights will collect the Imported Classes for all the devices in your environment on which the class exists.

Grant Inventory Read Only Role

As an Insights administrator, you can choose to grant others an Inventory Read Only role which lets them see the full policy but not change it.

To grant an Insights Inventory Read Only role to someone with a Default role:

1. On the Permissions page, click **Permissions** to the right of the Default role.

2. In the **Role Permissions** window that opens, expand the **InsightsSettings** section and enable 'ViewInventoryPolicy'.