Recast

Web Dashboards

Last Modified on 2026-09-17

Right Click Tools Dashboards

Within your Recast Management Server's **Dashboards** section, you can open the web versions of Right Click Tools dashboards:

- AD Cleanup
- BitLocker
- LAPS
- Software Updates
- Agent Management

For details on each dashboard, see Web Dashboards docs in our Right Click Tools docs.

> These Right Click Tools web dashboards allow administrators to give users access to dashboards without granting them access to the Configuration Manager console.

Snapshots

The **Snapshots** page lists snapshots taken from Right Click Tools web dashboards or dashboard trends.

Users can view and delete snapshots if they are assigned **GetExecutionHistoryForJobID** and **GetActionExecutionGroup** permissions in your Recast Management Server settings.

Insights Warranty Information Dashboard

The Insights **Warranty Information** page offers a detailed view of current warranties for devices managed in Microsoft Intune.


Prerequisites

- Right Click Tools Insights license
- Insights installed with Recast Management Server and Recast Proxy
- Recast Proxy configured for warranty information collection
- Service connection from your Recast Management Server to Entra ID (Azure Active Directory)
- The following Application permission added in the Microsoft Graph API for the application:
  - DeviceManagementManagedDevices.Read.All

To view the Warranty Information dashboard in your Recast Management Server, navigate to **Insights** > **Warranty Information**. The page displays data in both a dashboard view and a devices view.

Dashboard View

The dashboard view displays three charts:



- **Devices by Warranty Status**: Displays the number of devices according to warranty status (Active, Expiring Soon, Expired, Unknown).
  Expiring soon means that the warranty will expire within 120 days. The warranty status may be unknown if the warranty collection process has not yet completed.
- **Devices by Manufacturer**: Shows device information for the top five most frequent vendors in your environment. Click on a vendor for a filtered view of devices from that manufacturer.
- **Warranty Expiration Timeline**: Shows warranty expiration by month over the year to come.


TIP: You can resize the cards or drag-and drop them into a different layout. Refreshing the page returns the cards to their default positions.

Devices View

The **Warranty Information** page's Devices tab shows additional device warranty details. You can sort, filter, add, remove, and resize columns, and search all device warranty information. There is also an option to **Export to CSV** which can export unfiltered and filtered data.

TIP: You can resize, lock, add, and delete columns to customize your Devices view. Click the vertical ellipsis next to a column heading to see options.

Recast



The Devices tab displays the following warranty information:

- Device Name
- Primary Intune User
- Manufacturer
- Model
- Serial Number
- Remaining Coverage (in days)
- Warranty Start Date
- Warranty End Date
- Device Age