Recast

Mail Settings

Last Modified on 2026-09-28

Application Workspace lets you configure multiple mail servers. For example, you can use a mail server to send messages after a scheduled task has run.

Mail servers list

This list displays all mail servers currently available in the Application Workspace System.

Selecting multiple table rows

- Adjacent rows: Click on the first row, hold down the Shift key, click on the last row in the range
- Non-adjacent rows: Hold the Ctrl or Cmd key and click on each row you want to select
- Adjacent rows, using only the mouse: Click and hold the left mouse button on the first row, then drag the cursor up or down across the rows to highlight the desired ones

Table toolbar

To create a new mail server, click on the **Create** button; to view the details of a mail server or edit it, double-click its entry or select the mail server and click the **Edit** button.

The **Test** button opens the **Test email** dialog box where you can specify a target email address where you want to send a test email.

Views gives you control on how the table is displayed.
The default view contains all your mail servers in alphabetic ascending order, and the following columns: **Name**, **Type** and **Priority**.
You can create your own personalized view of the table, by filtering the mail servers or adding/deleting columns and clicking **Save as** in the drop-down menu of **Views**.

Detailed view of a mail server

See below the description of each screen in the detailed view of a mail server, and what actions you can perform in each of them.

Overview screen

Test – Opens the **Test email** dialog box where you can specify a target email address where you want to send a test email.
Priority – When trying to send an email Application Workspace will first use the mail server that has the lowest number in the priority field. If not available, it will continue with the next server in the list that has a higher priority.

Settings screen

SMTP

Server – The address of the mail server.
Secure – Whether or not a secure connection is required.
Port – The port used for the connection.
From – The mail address used to send the emails.

Recast

Authentication section

Here you can choose whether or not authentication is required for this mail server and configure the username and password for it.

Microsoft Graph

Client ID – The Application ID corresponding to your Microsoft Entra ID (Azure AD) app registration.
Tenant ID – An entity that typically encompasses an organization within Microsoft Entra ID (Azure AD).
Client secret – The Microsoft Entra ID (Azure AD) app registration secret.
From – The mail address used to send the emails.

> Microsoft Entra ID
> In Microsoft Entra ID, you need to add the *Mail.Send* permission to your app registration. For more details, see How to configure the Microsoft Graph mail server.

Auditing screen

View a comprehensive log of changes to this mail server, displaying the identity behind each modification.
This screen is available only if the auditing is enabled in the Database Event Collector. For more information, see Auditing.

Further reading

How to configure the Microsoft Graph mail server
Find your Microsoft Entra tenant ID (Microsoft documentation)