

## Device Collection Members

Last Modified on 04.16.26

### Get-LiquitDeviceCollectionMember

#### Synopsis

This command displays a list of devices that are members of a specific device collection.

#### Syntax

```
Get-LiquitDeviceCollectionMember  
[-DeviceCollection] <DeviceCollection[]>  
[-LiquitContext <LiquitContext>]  
[<CommonParameters>]
```

#### Example

The following script lists all available devices from the selected device collection:

```
$deviceCollection = Get-LiquitDeviceCollection -id 00000000-0000-0000-0000-000000000000  
Get-LiquitDeviceCollectionMember -DeviceCollection $deviceCollection
```

### Add-LiquitDeviceCollectionMember

#### Synopsis

This command adds a device to a collection.

#### Syntax

```
Add-LiquitDeviceCollectionMember  
[-DeviceCollection] <DeviceCollection>  
[-Device] <Device[]>  
[-LiquitContext <LiquitContext>]  
[-WhatIf]  
[-Confirm]  
[<CommonParameters>]
```

#### Example

The following script adds a specific device to a specific collection:

```
$device = Get-LiquitDevice -id 00000000-0000-0000-0000-000000000000  
$deviceCollection = Get-LiquitDeviceCollection -id 00000000-0000-0000-0000-000000000000  
Add-LiquitDeviceCollectionMember -DeviceCollection $deviceCollection -Device $device
```

# Recast

## Parameters

Name	Value	Description	Required	Default value
DeviceCollection	<DeviceCollection>	The collection to which you add the device.	Yes	
Device	<Device[]>	The device to add to the collection.	Yes	
LiquitContext	<LiquitContext>	Determines the selected zone.	No	Default

## Remove-LiquitDeviceCollectionMember

### Synopsis

This command removes a device from a collection.

### Syntax

```
Remove-LiquitDeviceCollectionMember  
[-DeviceCollection] <DeviceCollection>  
[-Device] <Device[]>  
[-LiquitContext <LiquitContext>]  
[-WhatIf]  
[-Confirm]  
[<CommonParameters>]
```

### Example

The following script removes the selected device from the selected collection:

```
$device = Get-LiquitDevice -id 00000000-0000-0000-0000-000000000000  
$deviceCollection = Get-LiquitDeviceCollection -id 00000000-0000-0000-0000-000000000000  
Remove-LiquitDeviceCollectionMember -DeviceCollection $deviceCollection -Device $device
```

## Parameters

Name	Value	Description	Required	Default value
DeviceCollection	<DeviceCollection>	The collection from which you remove the device.	Yes	
Device	<Device[]>	The device to remove from the collection.	Yes	
LiquitContext	<LiquitContext>	Determines the selected zone.	No	Default

---