

User Collection Members

Last Modified on 04.16.26

Get-LiquitUserCollectionMembers

Synopsis

This command displays a list of users that are members of a specific user collection.

Syntax

```
Get-LiquitUserCollectionMembers  
  [-UserCollection] <UserCollection[]>  
  [-LiquitContext <LiquitContext>]  
  [<CommonParameters>]
```

Example

The following script lists all available users from the selected user collection:

```
$UserCollection = Get-LiquitUserCollection -id 00000000-0000-0000-0000-000000000000  
Get-LiquitUserCollectionMembers -UserCollection $UserCollection
```

Add-LiquitUserCollectionMember

Synopsis

This command adds a user to a collection.

Syntax

```
Add-LiquitUserCollectionMember  
  [-UserCollection] <UserCollection>  
  [-User] <User[]>  
  [-LiquitContext <LiquitContext>]  
  [-Whatif]  
  [-Confirm]  
  [<CommonParameters>]
```

Example

The following script adds a specific user to a specific collection:

```
$User = Get-LiquitUser -id 00000000-0000-0000-0000-000000000000  
$UserCollection = Get-LiquitUserCollection -id 00000000-0000-0000-0000-000000000000  
Add-LiquitUserCollectionMember -UserCollection $UserCollection -User $User
```

Parameters

Name	Value	Description	Required	Default value
UserCollection	<UserCollection>	The collection to which you add the user.	Yes	
User	<User[]>	The user to add to the collection.	Yes	
LiquitContext	<LiquitContext>	Determines the selected zone.	No	Default

Remove-LiquitUserCollectionMember

Synopsis

This command removes a user from a collection.

Syntax

```
Remove-LiquitUserCollectionMember  
  [-UserCollection] <UserCollection>  
  [-User] <User[]>  
  [-LiquitContext <LiquitContext>]  
  [-Whatif]  
  [-Confirm]  
  [<CommonParameters>]
```

Example

The following script removes the selected user from the selected collection:

```
$User = Get-LiquitUser -id 00000000-0000-0000-0000-000000000000  
$UserCollection = Get-LiquitUserCollection -id 00000000-0000-0000-0000-000000000000  
Remove-LiquitUserCollectionMember -UserCollection $UserCollection -User $User
```

Parameters

Name	Value	Description	Required	Default value
UserCollection	<UserCollection>	The collection from which you remove the user.	Yes	
User	<User[]>	The user to remove from the collection.	Yes	
LiquitContext	<LiquitContext>	Determines the selected zone.	No	Default
