

User Collection Members

Last Modified on 2026-05-27

Get-LiquitUserCollectionMembers

This command displays a list of users that are members of a specific user collection.

Syntax

```
Get-LiquitUserCollectionMembers
  [-UserCollection] <UserCollection[]>
  [-LiquitContext <LiquitContext>]
  [<CommonParameters>]
```

Example

The following script lists all available users from the selected user collection:

```
$UserCollection = Get-LiquitUserCollection -id 00000000-0000-0000-0000-000000000000
Get-LiquitUserCollectionMembers -UserCollection $UserCollection
```

Add-LiquitUserCollectionMember

This command adds a user to a collection.

Syntax

```
Add-LiquitUserCollectionMember
  [-UserCollection] <UserCollection>
  [-User] <User[]>
  [-LiquitContext <LiquitContext>]
  [-WhatIf]
  [-Confirm]
  [<CommonParameters>]
```

Example

The following script adds a specific user to a specific collection:

```
$User = Get-LiquitUser -id 00000000-0000-0000-0000-000000000000
$UserCollection = Get-LiquitUserCollection -id 00000000-0000-0000-0000-000000000000
Add-LiquitUserCollectionMember -UserCollection $UserCollection -User $User
```

Parameters

Name	Value	Description	Required	Default value
------	-------	-------------	----------	---------------

Recast

Name	Value	Description	Required	Default value
UserCollection	<UserCollection>	The collection to which you add the user.	Yes	
User	<User[]>	The user to add to the collection.	Yes	
LiquitContext	<LiquitContext>	Determines the selected zone.	No	Default

Remove-LiquitUserCollectionMember

This command removes a user from a collection.

Syntax

```
Remove-LiquitUserCollectionMember  
[-UserCollection] <UserCollection>  
[-User] <User[]>  
[-LiquitContext <LiquitContext>]  
[-WhatIf]  
[-Confirm]  
[<CommonParameters>]
```

Example

The following script removes the selected user from the selected collection:

```
$User = Get-LiquitUser -id 00000000-0000-0000-0000-000000000000  
$UserCollection = Get-LiquitUserCollection -id 00000000-0000-0000-0000-000000000000  
Remove-LiquitUserCollectionMember -UserCollection $UserCollection -User $User
```

Parameters

Name	Value	Description	Required	Default value
UserCollection	<UserCollection>	The collection from which you remove the user.	Yes	
User	<User[]>	The user to remove from the collection.	Yes	
LiquitContext	<LiquitContext>	Determines the selected zone.	No	Default