

Reset Workspace

Last Modified on 2026-05-27

Reset-LiquitUserWorkspace

This command resets the workspace for a user.

Syntax

```
Reset-LiquitUserWorkspace  
[-User] <User[]>  
[-Items <bool>]  
[-Settings <bool>]  
[-LiquitContext <LiquitContext>]  
[-WhatIf]  
[-Confirm]  
[<CommonParameters>]
```

```
Reset-LiquitUserWorkspace  
[-ID] <string[]>  
[-Items <bool>]  
[-Settings <bool>]  
[-LiquitContext <LiquitContext>]  
  [-WhatIf]  
[-Confirm]  
[<CommonParameters>]
```

```
Reset-LiquitUserWorkspace  
[-IdentityRef] <IdentityRef[]>  
[-Items <bool>]  
[-Settings <bool>]  
[-LiquitContext <LiquitContext>]  
[-WhatIf]  
[-Confirm]  
[<CommonParameters>]
```

Examples

Example 1: Reset-LiquitUserWorkspace

```
Reset-LiquitUserWorkspace -id "source\00000000-0000-0000-0000-000000000000" -Items $true
```

Example 1: Reset-LiquitUserWorkspace

```
$identity = Get-LiquitIdentity -id "source\00000000-0000-0000-0000-000000000000"  
Reset-LiquitUserWorkspace -User $identity -Items $true
```

This command resets all the settings of the selected user.

Parameters

Name	Value	Description	Required	Default value
------	-------	-------------	----------	---------------

Recast

Name	Value	Description	Required	Default value
User	<User[]>	The user whose workspace you want to reset.	User only	
ID	<string[]>	The GUID of the user whose workspace you want to reset.	ID only	
IdentityRef	<IdentityRef[]>	The identity reference of the user whose workspace you want to reset.	IdentityRef only	
Items	<bool>	If true, this cmdlet resets the workspace items of the user.	No	
Settings	<bool>	If true, this cmdlet resets the workspace settings of the user.	No	
LiquitContext	<LiquitContext>	Determines the selected zone.	No	Default
