

Send Notification

Last Modified on 05.06.25

The **Send Notification** tool sends a custom notification to a device.


This tool can be run on single or multi-selected devices. A similar tool is designed for [device collections](#).

For a video walkthrough, see [Right Click Tools: Send Notification](#).

To run the tool:

1. Right-click on a device.
2. Select **Right Click Tools > Console Tools > Send Notification**.

The **Send Notification** window will open.



The screenshot shows the 'Send Notification' window with the following components:


- Title:** A text input field.
- Message:** A text input field.
- Logo Image:** A text input field with a 'Browse...' button.
- Send Notification:** A button at the bottom of the form.
- Advanced Settings:** A section with a dropdown arrow, containing a table of notification methods.

Status	Description	Devices
Pending	Devices waiting for notification to be sent	1
RecastToastSent	A toast notification with Title, Message, and Logo Image was successfully sent to these devices using the Recast Toast utility	0
CmClientToastSent	A toast notification with Title and Message was successfully sent to these devices using the Configuration Manager client	0
WindowsDialogMessageSent	A notification with Title and Message was successfully sent to these devices using the Windows Dialog API	0

3. Expand **Advanced Settings** to choose the type(s) of notification to send:

- Recast Toast Notification
- Configuration Manager Client Toast Notification
- Windows Popup Message

NOTE: The notification will only be sent using the first successful method.



The screenshot shows the 'Send Notification' window with the 'Advanced Settings' section expanded. It contains the following text and checkboxes:

Select the methods to attempt to send notification. Only the first successful will be sent, in this order.

- ☒ Send Recast Toast Notification
- ☒ Send CM Client Toast Notification
- ☒ Send Windows Popup Message

4. Add a **Logo Image** in PNG, JPG, or BMP format to send with your Recast Toast notification (optional).

5. Click **Send Notification**.

Recast Permissions

SystemInformation plugin	SendRecastToastNotification permission
	SendMessageAllUsers permission
ConfigMgrClient plugin	SendCmClientToastNotification permission

Copyright © 2025 Recast Software Inc. All rights reserved.