


Install an Agent Gateway

Last Modified on 08.30.23

A single Agent Gateway is automatically deployed and authorized when you install Recast Management Server. You can also install additional Agent Gateways, to accommodate all of your Recast Agents. Each Agent Gateway must be installed on a different server. Agent Gateway software is available from the [Recast Portal](#).


To configure an Agent Gateway:

1. On the Agent Gateway installer's IIS Configuration page, specify the **Server Name** in FQDN format (server.domain.local) and **IIS Port** for the Agent Gateway.



The screenshot shows the 'IIS Configuration' dialog box in the 'Recast Agent Gateway - Setup' application. The dialog has a title bar with a close button (X) and a Recast logo. Below the title bar, the text 'IIS Configuration' is displayed. There are two input fields: 'Server Name' with the value 'GWSERVER' and 'IIS Port' with the value '444'. At the bottom of the dialog, there is a help icon (question mark in a circle) and three buttons: 'Previous', 'Next', and 'Cancel'.


2. On the Certificate Configuration page, select an existing certificate, or generate a self-signed certificate.



The screenshot shows the 'Certificate Configuration' dialog box in the 'Recast Agent Gateway - Setup' application. The dialog has a title bar with a close button (X) and a Recast logo. Below the title bar, the text 'Certificate Configuration' is displayed. There are two radio button options: 'Generate Self-Signed Certificate' (which is selected) and 'Use Existing IIS Certificate'. Below the options is a large empty rectangular area. At the bottom of the dialog, there is a help icon (question mark in a circle) and three buttons: 'Previous', 'Next', and 'Cancel'.

3. Click **Test Connection** to check that the Agent Gateway can connect to your Recast Management Server.

Recast



4. With a successful connection test, click **Install**.
5. When the installation completes, click **Finish** to close the installer.

Verify Agent Gateway Installation

In the Recast Management Server interface, navigate to **Administration > Agent Gateways** and check that the new Agent Gateway is connected and authorized. If you've installed an Agent Gateway on a separate server, you may need to [manually authorize it in RMS](#).

For information on the hardware needed for Agent Gateway servers, see [Recast Management Server System Requirements](#).

To learn more about installing your Recast Management Server with an additional Gateway, see [Network Architecture: RMS with Standalone Agent Gateway](#).

The Agent Gateway SQLite file is located at `C:\Users\Recast Agent Gateway\AppData\Roaming\Recast Software\Recast Agent Gateway`
