


Install an Agent Gateway

Last Modified on 08.30.23

A single Agent Gateway is automatically deployed and authorized when you install Recast Management Server. You can also install additional Agent Gateways, to accommodate all of your Recast Agents. Each Agent Gateway must be installed on a different server. Agent Gateway software is available from the [Recast Portal](#).


To configure an Agent Gateway:

1. On the Agent Gateway installer's IIS Configuration page, specify the **Server Name** in FQDN format (server.domain.local) and **IIS Port** for the Agent Gateway.




The screenshot shows the 'IIS Configuration' window of the Recast Agent Gateway Setup. It features two input fields: 'Server Name' with the value 'GWSERVER' and 'IIS Port' with the value '444'. The window includes a Recast logo in the top right, a help icon in the bottom left, and 'Previous', 'Next', and 'Cancel' buttons at the bottom.

2. On the Certificate Configuration page, select an existing certificate, or generate a self-signed certificate.



The screenshot shows the 'Certificate Configuration' window of the Recast Agent Gateway Setup. It has two radio buttons: 'Generate Self-Signed Certificate' (which is selected) and 'Use Existing IIS Certificate'. Below the buttons is a large empty rectangular area. The window includes a Recast logo in the top right, a help icon in the bottom left, and 'Previous', 'Next', and 'Cancel' buttons at the bottom.

3. Click **Test Connection** to check that the Agent Gateway can connect to your Recast Management Server.



4. With a successful connection test, click **Install**.

5. When the installation completes, click **Finish** to close the installer.

Verify Agent Gateway Installation

In the Recast Management Server interface, navigate to **Administration > Agent Gateways** and check that the new Agent Gateway is connected and authorized. If you've installed an Agent Gateway on a separate server, you may need to [manually authorize it in RMS](#).

For information on the hardware needed for Agent Gateway servers, see [Recast Management Server System Requirements](#).

To learn more about installing your Recast Management Server with an additional Gateway, see [Network Architecture: RMS with Standalone Agent Gateway](#).

The Agent Gateway SQLite file is located at `C:\Users\Recast Agent Gateway\AppData\Roaming\Recast Software\Recast Agent Gateway`