

Add RMS to Right Click Tools Standalone

Last Modified on 05.03.24

If you are using Right Click Tools Enterprise in Standalone mode, you can choose to add Recast Management Server to your deployment at any time.

Recommended Workflow


1. [Install Recast Management Server with Recast Proxy](#) .
2. [Configure Recast Management Server for Right Click Tools](#) .
3. [Connect Right Click Tools to Recast Management Server](#) .
4. [Check the Right Click Tools connection to RMS](#).
5. [Upload your Enterprise license to Recast Management Server](#) .

Connect Right Click Tools to Recast Management Server

Once you've installed Recast Management Server with Recast Proxy, connect Right Click Tools to your Recast Management Server in the Configure Recast Console Extension application.

To add your Recast Management Server URL:

1. From the Windows Start menu, open **Configure Recast Console Extension** .
2. On the **General** tab, enter the **Recast Management Server** URL, including `https://` at the beginning.



3. Leave the **Run in ConfigMgr Console Process** option disabled.

NOTE: Enabling the **Run in ConfigMgr Console Process** option can be useful when troubleshooting console crashes or when security software might be blocking the Right Click Tools Console Extension application from running. It allows


you to run in the Microsoft.ConfigurationManagement process instead.

4. Click **Save**.
5. If the Configuration Manager console is open, close and reopen it.

Check Recast Management Server Connection

To check that Right Click Tools is connected to RMS:

1. Open the Assets and Compliance section in the Configuration Manager console where you installed Right Click Tools.
2. Click **Recast Software** in the navigation panel.
3. Check that the **Installation Information** section shows your **Remote Server Status** as 'Connected'.



The screenshot displays the Recast Software interface within the Configuration Manager console. The left-hand navigation pane is titled 'Assets and Compliance' and lists various categories, with 'Recast Software' selected at the bottom. The main content area features a dark header with the Recast Software logo and the text 'RECAST SOFTWARE'. Below the header, the page is divided into several sections: 'Welcome to Right Click Tools' with a 'Contact Support' button, 'Getting Started' with a brief description, and 'Installation Information' which includes a table of system details.

Installation Information	
Desktop Installed Version:	4.8.2110.3803
Server Installed Version:	4.8.2109.4101
Enterprise License:	<input checked="" type="checkbox"/>
License Expiration Date:	9/14/2024 12:00:00 AM
Remote Server Status:	Connected
License Org:	Recast Software

Upload Licenses to Recast Management Server

Once you've connected Right Click Tools to your Recast Management Server, you can upload your licenses on the **Licenses** page in RMS. Your licenses are available from the [Recast Portal](#).