

Licensing

Last Modified on 04.16.26

Check your Application Workspace license status and how many licenses are in use for the current zone.

Home / Manage / System / Licensing

Licensing

License state

Active

License

Liquit Workspace with Access Manager and Release & Patch Management

Licensed to

████████████████████

Expires

Wednesday, December 31, 2025

License type

NFR

Purchased license type

Named User

2 Named User licenses in use



Install license

Refresh license

License usage report

Remove license

License state – The state of the current license. It should always be active.

License – Shows which product/edition is licensed. For a full overview of Recast products and the differences, see our [website](#).

Licensed to – The virtual host name for which this license is granted. It needs to match the primary domain (Virtual Host). Changing the primary domain without updating the license will render it invalid and will disable the zone.

Expires – The zone will no longer be usable after this date, unless the license is renewed.

License type – The license type issued to your organization.

Purchased license type – The method used to track the license usage.

The informational bar

It displays the number of licenses you have purchased and how many of those are in use. Note that certain license types do not have information related to the number of purchases.

In case more users are in use than the number of licenses that have been purchased, a portion of the bar will be displayed red. In this case, we recommend you contact the support department to purchase additional licenses, in order to prevent disruption.

2 Named User licenses in use



A license expiration warning will be shown if the license expires within 14 days. We recommend you renew the license before it expires, otherwise the Application Workspace will become unavailable.

Install license button

Opens a dialog box in which you can enter your license key. you have been provided with upon purchasing Application Workspace.

Recast

Activate license



License state

Active

Virtual host

██████████

License key *

AAAAA-BBBBBB-CCCCC-DDDDD-EEEE

Confirm

Cancel

Refresh license button

With the help of this button you can manually update the current state of the license with the latest information. The license information is updated automatically by the [Refresh Zone Licenses](#) scheduled task, which is preconfigured.

License usage report

The license usage report can be opened if you double click on the informational bar or the **License usage report** button.

The dialog box that opens displays an overview of your purchase license.

License usage report



Report generated at

5/7/2025 12:00:20 AM

Unique users with login access

3

Licenses in use

2

Permissions that grant login access

Purchased license type

Named User

Excluded users

1

Purchased licenses

0

Identity ↑	Identity source	Users
admin	LOCAL	1
Everyone	LOCAL	3
User 1	LOCAL	1
User 2	LOCAL	1
user collection	LOCAL	2

Close

The following aspects must be taken into consideration when analyzing the license usage:

- Active licenses represent workspace that are active. In other words, when a user gets permission to use the Application Workspace, it will count as a license in use
- By default the LOCAL\Admin is excluded from the license count.

Recast

- if a user is part of multiple groups/contexts/collections, it is counted as one.
- Disabled users are not counted.

For privacy reasons, the list of permissions that grants login access and the user count is accessible only from within the zone. This information is not accessible from the [Zone management](#) interface.

Remove license button

After you click on this button, Application Workspace will stop functioning. Also, after you successfully login the license dialog box will be displayed.
