

Zone Licenses

Last Modified on 2026-05-27

Install-LiquitZoneLicense

This command is used to install a new license for a zone.

Syntax

```
Install-LiquitZoneLicense  
[-Zone] <Zone[]>  
[-Key] <string>  
[-LiquitContext <LiquitContext>]  
[-Whatif]  
[-Confirm]  
[<CommonParameters>]
```

Example script

To install the license key in the specified zone:

```
$zone =Get-LiquitZone -ID 00000000-0000-0000-0000-000000000000  
Install-LiquitZoneLicense -Zone $zone -Key 00000-00000-00000-00000-00000
```

Update-LiquitZoneLicense

This command refreshes the license of the zone.

Syntax

```
Update-LiquitZoneLicense  
[-Zone] <Zone[]>  
[-LiquitContext <LiquitContext>]  
[-Whatif]  
[-Confirm]  
[<CommonParameters>]
```

Example

The following script refreshes the license of the specified zone:

```
$zone =Get-LiquitZone -ID 00000000-0000-0000-0000-000000000000  
Update-LiquitZoneLicense -Zone $zone -Key 00000-00000-00000-00000-00000
```

Parameters

Name	Value	Description	Required	Default value
------	-------	-------------	----------	---------------

Recast

Name	Value	Description	Required	Default value
Zone	<Zone[]>	The zone for which you want to refresh the license.	Yes	
LiquitContext	<LiquitContext>	Determines the selected zone.	No	Default

Remove-LiquitZoneLicense

This command removes a license of a zone.

Syntax

```
Remove-LiquitZoneLicense  
[-Zone] <Zone[]>  
[-LiquitContext <LiquitContext>]  
[-Whatif]  
[-Confirm]  
[<CommonParameters>]
```

Example script

To remove the license from the specified zone:

```
$zone = Get-LiquitZone -ID 00000000-0000-0000-0000-000000000000  
Remove-LiquitZoneLicense -Zone $zone
```

Parameters

Name	Value	Description	Required	Default value
Zone	<Zone[]>	The zone for which you want to remove the license.	Yes	
LiquitContext	<LiquitContext>	Determines the selected zone.	No	Default