

Right Click Tools Upgrades

Last Modified on 01.29.25

Upgrade Right Click Tools Version

Follow these steps to update Right Click Tools implementations connected to a Recast Management Server. For Right Click Tools Standalone, see Upgrade Right Click Tools Standalone Version.

Upgrading Right Click Tools to the latest release lets you take advantage of new features, performance improvements and bug fixes. For all the details on what's new, see the release notes.

Newer versions of Right Click Tools, Recast Management Server, Recast Proxy, and Recast Agents can be installed in place right over existing versions. To upgrade Right Click Tools versions older than 4.x, we recommend uninstalling the old version before deploying a newer release.

NOTE: Version 5.x and 4.x components are not compatible. You must upgrade Right Click Tools, Recast Management Server, Recast Proxy and Recast Agents to a v5 release for Right Click Tools to work correctly.

Upgrade Sequence

When upgrading Right Click Tools, install new versions of the applications and components in your Recast deployment in the following order:

1. Recast Management Server

Where Recast Management Server and Recast Proxy are installed on the same computer, both are updated when you upgrade the Recast Management Server version. If your Recast Proxy is installed on a different device than RMS, you'll need to update it separately before updating Right Click Tools.

2. Right Click Tools

You must run the Right Click Tools installer anywhere you have Right Click Tools installed on a Configuration Manager console.

3. Recast Agents

NOTE: You can check that the upgrade is complete within **Programs and Features**.

Upgrade Your Recast Management Server

To upgrade your Recast Management Server:

- 1. Download the installation file from the Recast Portal.
- 2. Double-click the downloaded installation file.
- 3. Follow the installer prompts.

Upgrade Right Click Tools and Recast Agents with Application Manager

We recommend upgrading to newer Right Click Tools and Recast Agent versions using Application Manager. Your Right Click Tools Enterprise license alone gives you access to Application Manager. In the absence of Application Manager licensing, the AM software catalog is limited to the Right Click Tools and Recast Agent applications.


Prerequisites for Deploying Agents using Application Manager:

- Recast Management Server is running Recast Software version 5.4 or later, as that version introduces Application
 Manager in RMS.
- Required proxy permissions for Application Manager are in place

TIP: Alternatively, you can choose to upgrade Right Click Tools and Recast Agents manually by downloading and running new versions of the RCT and Agent installers.

To deploy the Right Click Tools and Recast Agent applications with Application Manager:

- 1. If you haven't already done so, complete your initial AM setup, skipping the Setup Wizard's Define Deployment Processes step.
- 2. Add a deployment process for the 'Right Click Tools' and 'Recast Agent' applications.
- 3. On the Deployment Process Details page, click the Settings cog to open your Global Deployment Process settings.



- 4. On the Advanced tab, set Additional Installation Parameters:
 - **Silent Agent Install**: Add the **RCTENTERPRISESERVER=https://<RMS URL>:<Port>** parameter to your install string, substituting the URL and port number for your Recast Management Server.
 - Connect Recast Agents to a specific Agent Gateway: Add the AGENTGATEWAY=https://<AG URL>:<Port>
 parameter to your install string, substituting the URL and port number for your Agent Gateway

NOTE: Adding these parameters in Application Manager's deployment settings enables deployed Recast Agents to connect to your Recast Management Server, verify that the certificate used by the RMS is trusted, and successfully enroll with the RMS. Recast Agents are required to enroll with the RMS before they can communicate with a Recast Agent Gateway and be used to run actions.

Video Walkthrough

See Recast Application Deployment with Application Manager on our YouTube channel.

Re-authorize an Agent Gateway

After upgrading to new Recast Software versions, you may need to re-authorize your Right Click Tools server as an Agent Gateway.

To re-authorize an Agent Gateway:

- 1. In the Recast Management Server interface, navigate to **Agent Gateways**.
- 2. Click the Edit icon to the right of the computer you want to authorize as an Agent Gateway.
- 3. Enable the Authorized checkbox and click Save.

Silent install: Right Click Tools with Recast Management Server

Add the parameter RCTENTERPRISESERVER=https://<FQDN>:<Port> to your install string so your console can connect to the Recast Management Server. Substitute the FQDN for your RMS server followed by the port number. The default port used by RMS is TCP 444.

Example:

msiexec.exe /i "Right Click Tools.msi" /qn RCTENTERPRISESERVER="https://RMS.RecastDomain.com:444"

Uninstall Right Click Tools Version

You can revert to a previous v5 release of Right Click Tools by downloading an archived release and installing it over the more recent software version.

To download an archived release:

- 1. Log into the Recast Portal.
- 2. Click the **Resources** tab and select **Archived Releases**.
- 3. In the **Download** column, click the blue download icon for the software version you want to install.

Enable/Disable Right Click Tools Update Notifications

By default, your Right Click tools will display a notification whenever a new software version is released. You can view or change your notification settings in either the Recast Management Server interface or the Configure Recast Console Extension application.

To change your notification settings in Recast Management Server:

- 1. Open your Recast Management Server and navigate to **Administration** > **Settings**.
- 2. Set **DisplayUpdatePromptsToUsers** to 'true' or 'false' depending on whether you want to be notified when Recast Software releases a software update that includes new features and bug fixes.
- 3. Set **DisplayBugfixUpdatePromptsToUsers** to 'true' or 'false' depending on whether you want to be notified when Recast Software releases a software update that includes only bug fixes.

To change your notification settings in Configure Recast Console Extension:

- 1. Access the Configure Recast Console Extension from your Configuration Manager console by navigating to the Recast Software node.
- 2. In the 'How Can We Help?' section, click **Configure Recast** .
- 3. On the General tab. enable or disable Automatically Check For Updates.
- 4. Click **Save** to apply your changes.

Add RMS to Right Click Tools Standalone

If you are using Right Click Tools Enterprise in Standalone mode, you can choose to add Recast Management Server to your deployment at any time.

Recommended Workflow


- 1. Install Recast Management Server with Recast Proxy.
- 2. Configure Recast Management Server for Right Click Tools.
- 3. Connect Right Click Tools to Recast Management Server .
- 4. Check the Right Click Tools connection to RMS.
- 5. Upload your Enterprise license to Recast Management Server.

Connect Right Click Tools to Recast Management Server

Once you've installed Recast Management Server with Recast Proxy, connect Right Click Tools to your Recast Management Server in the Configure Recast Console Extension application.

To add your Recast Management Server URL:

- 1. From the Windows Start menu, open **Configure Recast Console Extension**.
- 2. On the **General** tab, enter the **Recast Management Server** URL, including https:// at the beginning.



3. Leave the **Run in ConfigMgr Console Process** option disabled.


NOTE: Enabling the **Run in ConfigMgr Console Process** option can be useful when troubleshooting console crashes or when security software might be blocking the Right Click Tools Console Extension application from running. It allows you to run in the Microsoft.ConfigurationManagement process instead.

- 4. Click Save.
- 5. If the Configuration Manager console is open, close and reopen it.

Check Recast Management Server Connection

To check that Right Click Tools is connected to RMS:

- 1. Open the Assets and Compliance section in the Configuration Manager console where you installed Right Click Tools.
- 2. Click **Recast Software** in the navigation panel.
- 3. Check that the Installation Information section shows your Remote Server Status as 'Connected'.



Upload Licenses to Recast Management Server

Once you've connected Right Click Tools to your Recast Management Server, you can upload your licenses on the **Licenses** page in RMS. Your licenses are available from the Recast Portal.

Copyright © 2025 Recast Software Inc. All rights reserved.