

## Recast Proxy Permission Requirements

Last Modified on 10.24.25

## Right Click Tools

Access web dashboards and trends Schedule Builder actions Schedule kiosk profile application	<ul> <li>Local admin access on the server where the proxy is being installed</li> <li>Read permissions in Active Directory</li> <li>db_datareader in the Configuration Manager SQL server database</li> <li>Read-only access to the Configuration Manager console (Read-only Analyst security role in ConfigMgr)</li> </ul>
Run actions as a service account	<ul> <li>Local admin access on any device that actions will be run against</li> <li>Read/Write permissions in Active Directory (Write only required to delete devices from AD)</li> <li>Appropriate ConfigMgr Security Role for intended actions in the Configuration Manager console (Full Administrator for all actions)</li> <li>Permission to MBAM, if applicable</li> </ul>
Elevate permissions	Local admin access on all devices managed by Right Click Tools
Add or remove from collections	Permission to modify a collection in Configuration Manager     configmgr collection > modify permission
Fast Channel support	<ul> <li>Permission to run scripts in Configuration Manager</li> <li>If using Read-only Analyst in ConfigMgr as your base security role, also grant the following privileges:</li> <li>Collection &gt; Run Script = Yes SMS Scripts &gt; Read = True</li> </ul>

## Right Click Tools Insights

To collect warranty information	<ul> <li>Local admin access on the server where the proxy is being installed</li> <li>Read permissions in Active Directory</li> <li>db_datareader in the Configuration Manager SQL server database</li> <li>Read-only access to the Configuration Manager console (Read-only</li> </ul>
	<ul> <li>Analyst security role in ConfigMgr)</li> <li>NOTE: These permissions match those required to access web dashboard and trends in Right Click Tools</li> <li>Internet access for the proxy account in order for the Recast Managemen Server to reach our API at https://warranty.recastsoftware.com over TCP 443</li> </ul>
To collect warranty information if RMS is installed on a server other than your ConfigMgr SQL database	<ul> <li>Add proxy account to the SMS_SiteSystemToSiteServerConnection_MP_<yoursitecode> local grou on that server, allowing it to read/write to your inboxes\auth\ddm.box</yoursitecode></li> </ul>

## Right Click Tools Patching



MECM Integration	<ul> <li>Grant any of the following built-in roles/role combinations to the proxy account:</li> </ul>
	Full Administrator
	<ul> <li>Operations Administrator</li> </ul>
	<ul> <li>Application Administrator and Compliance Settings Manager</li> </ul>
	<ul> <li>Application Administrator and Read-only Analyst</li> </ul>
	<ul> <li>Modify permissions to the SMB share (UNC path) that will be used to store downloaded applications</li> </ul>
	<ul> <li>Internet access for the proxy account used to access the application</li> </ul>
	catalog, check for new application versions, and download application
	media and icons.