Recast

Attributes

Last Modified on 2026-11-02

Get-LiquitAttribute

This command displays a list of all attributes associated with an entity. An attribute can be a package connection with a connector for example. Or it can be used to associate content with an uploaded type of action (e.g. “Install Uploaded File”).

Syntax

```
Get-LiquitAttribute
  [-Entity] <Entity>
  [-LiquitContext <LiquitContext>]
  [<CommonParameters>]

Get-LiquitAttribute
  [-Entity] <Entity>
  [-Type] {Unknown | System | Server | Zone | Tag | IdentitySource | Device | User | Group | DeviceCollection | Package | PackageSnapshot | ActionSet | Action | FilterSet | Filter | Workspace | Policy | Context | View | MailServer | License | Team | Authenticator | Connector | Credential | ScheduledTask | EntityFilter | Deployment | Content |  IdentityProvider | Certificate | SystemUpdate | MailTemplate | AuthContract | PersonalPackage | DeviceRegistration | ConditionSet | Category | EventCollector | ZoneDomain | UserCollection | Session | Variable | Permission | Resource | Task | Approval}
  [-LiquitContext <LiquitContext>]
  [<CommonParameters>]

Get-LiquitAttribute
  [-Entity] <Entity>
  [-ID] <string[]>
  [-LiquitContext <LiquitContext>]
  [<CommonParameters>]
```

Example

The following script displays all the attributes of the package:

```
$package = Get-LiquitPackage -id 00000000-0000-0000-0000-000000000000
Get-LiquitAttribute -Entity $package
```

New-LiquitAttribute

This command creates a new attribute.

Syntax

```
New-LiquitAttribute
  [-Entity] <Entity[]>
  [-ID] <string>
  [-Link <Entity>]
  [-Settings <hashtable>]
  [-LiquitContext <LiquitContext>]
  [-WhatIf]
  [-Confirm]
  [<CommonParameters>]
```

Example

The following script creates a new attribute and provides the link between the uploaded content and the action:

```
 $package = Get-LiquitPackage -id 00000000-0000-0000-0000-000000000000
 $packageSnapshot = Get-LiquitPackageSnapshot -Package $package -id
 $actionset = New-LiquitActionSet -Snapshot $packageSnapshot -Type Install
 $action = New-LiquitAction -Actionset $actionset -Type contentcopy -Enabled $true -Context Device -Settings @{con
tent= "executable.exe"; destination = "C:\destination\"} -name "Contentaction"
 $content = New-LiquitContent -Path "C:\path\executable.exe" -FileName "executable.exe"
 $attribute = New-LiquitAttribute -Entity $action -Link $content -ID “content” -Settings: @{filename = "executable.ex
e"}
```

Parameters

Name	Value	Description	Required	Default value
Entity	`<Entity[]>`	The entity to which you want to associate the attribute.	Yes	
ID	`<string>`	The ID that should be associated with the attribute (e.g. “Content”).	Yes	
Link	`<Entity>`	A link to another optional entity.	No	
Settings	`<Hashtable>`	The settings of the attribute.	Yes	
LiquitContext	`<LiquitContext>`	Determines the selected zone.	No	Default

Set-LiquitAttribute

This command edits the properties of an attribute.

Syntax

```
Set-LiquitAttribute
  [-Attribute] <Attribute[]>
  [-Link <Entity>]
  [-Settings <hashtable>]
  [-LiquitContext <LiquitContext>]
  [-WhatIf]
  [-Confirm]
  [<CommonParameters>]
```

Example

The following script updates an existing attribute:

```
$package = Get-LiquitPackage -id 00000000-0000-0000-0000-000000000000
Get-LiquitAttribute -Entity $package
Set-LiquitAttribute  -Settings @{filename = logo.png}
```

Parameters

Name	Value	Description	Required	Default value
Link	`<Entity>`	A link to another optional entity.	No	
Settings	`<Hashtable>`	The settings of the attribute.	No	
LiquitContext	`<LiquitContext>`	Determines the selected zone.	No	Default

Remove-LiquitAttribute

This command removes an attribute from the Application Workspace.

Syntax

```
Remove-LiquitAttribute
  [-Attribute] <Attribute[]>
  [-LiquitContext <LiquitContext>]
  [-WhatIf]
  [-Confirm]
  [<CommonParameters>]
```

Example

The following script removes the selected attribute from the Application Workspace:

```
$package = Get-LiquitPackage -id 00000000-0000-0000-0000-000000000000
$attribute = Get-LiquitAttribute -Entity $package
Remove-LiquitAttribute -Attribute $attribute
```

Recast

Parameters

Name	Value	Description	Required	Default value
Attribute	`<Context>`	The attribute you wish to remove.	Yes	
LiquitContext	`<LiquitContext>`	Determines the selected zone.	No	Default